Hortonworks DataFlow

Security

(June 9, 2017)

docs.cloudera.com

Hortonworks DataFlow: Security Copyright © 2012-2017 Hortonworks, Inc. Some rights reserved.



Except where otherwise noted, this document is licensed under Creative Commons Attribution ShareAlike 4.0 License. http://creativecommons.org/licenses/by-sa/4.0/legalcode

Table of Contents

1. Enabling Kerberos	1
1.1. Installing and Configuring the KDC	. 1
1.1.1. Use an Existing MIT KDC	. 1
1.1.2. Use an Existing Active Directory	. 2
1.1.3. Use Manual Kerberos Setup	. 2
1.1.4. (Optional) Install a new MIT KDC	. 3
1.2. Installing the JCE	
1.2.1. Install the JCE	
1.3. Enabling Kerberos on Ambari	. 7
1.4. Cluster Component Configuration Updates	
2. NiFi Authentication	
2.1. Enabling SSL with a NiFi Certificate Authority	
2.2. Enabling SSL with Existing Certificates	
2.3. (Optional) Setting Up Identity Mapping	
2.4. Generating Client Certificates	
2.5. Logging into NiFi After Enabling SSL	
3. SAM Authentication	
3.1. Logging into SAM for the First Time	
3.2. Logging In as a Different User	
4. Installing Ranger	
4.1. Ranger Installation Prerequisites	
4.2. Setting up Databases for Ranger	
4.2.1. Configuring MySQL for Ranger	
4.2.2. Configuring PostgreSQL for Ranger	
4.2.3. Configuring Oracle for Ranger	
4.3. Installing Ranger	
4.3.1. Start the Installation	
4.3.2. Customize Services	
4.3.3. Complete the Ranger Installation	
4.3.4. Advanced Usersync Settings	
4.3.5. Configuring Ranger for LDAP SSL	
4.3.6. Setting up Database Users Without Sharing DBA Credentials	
4.3.7. Updating Ranger Admin Passwords	
4.3.8. Enabling Ranger Plugins	
4.4. Adding Users to Ranger	
5. Authorization with Ranger	
5.1. Creating Policies for NiFi Access	
5.1.1. Creating Policies to View NiFi	
5.1.2. Allowing Users Read and Write Access	
5.1.2. Anowing osers need and write Access	
5.3. Create a Storm Policy	
6. NiFi Authorization	
6.1. Authorizer Configuration	
6.2. Authorizers.xml Setup	
6.2.1. Initial Admin Identity (New NiFi Instance)	
6.2.2. Legacy Authorized Users (NiFi Instance Upgrade)	
6.2.3. Cluster Node Identities	
6.3. Configuring Users & Access Policies	
0.5. Comiganing users & Access Funcies	10

6.3.1. Creating Users and Groups	. 78
6.3.2. Access Policies	. 80
6.3.3. Access Policy Configuration Examples	. 82
7. SAM Authorization	. 95
7.1. Roles and Permissions	95
7.2. Creating Users and Assigning Them to Roles	97
7.3. Sharing Resources	
7.3.1. Sharing an Environment	. 98
7.4. Sharing an Application	
7.5. SAM Authorization Limitations	. 99
8. Deploying SAM Applications in a Secure Cluster	100
8.1. Connecting to a Secure Service that Supports Delegation Tokens	100
8.2. Connecting to Secure Kafka	101
8.3. Securing SAM – An End-to-End Workflow	102
8.3.1. Understanding the End-to-End Workflow	102

List of Tables

2.1. Identity mapping values	
4.1. Ranger DB Host	27
4.2. Driver Class Name	
4.3. Ranger DB Username Settings	28
4.4. JDBC Connect String	28
4.5. DBA Credential Settings	29
4.6. UNIX User Sync Properties	. 36
4.7. LDAP/AD Common Configs	37
4.8. LDAP/AD User Configs	
4.9. LDAP/AD Group Configs	39
4.10. UNIX Authentication Settings	44
4.11. LDAP Authentication Settings	
4.12. AD Settings	48
4.13. LDAP Advanced ranger-ugsync-site Settings	52
4.14. AD Advanced ranger-ugsync-site Settings	53
4.15. Advanced ranger-ugsync-site Settings for LDAP and AD	53
5.1. Policy Details	70
5.2. Allow Conditions	70
5.3. Policy Details	72
5.4. Allow Conditions	72
5.5. Storm User and Group Permissions	73
7.1. Role and Permission Matrix	96

1. Enabling Kerberos

To enable Kerberos on Ambari, complete the following steps:

- 1. Installing and Configuring the KDC [1]
- 2. Installing the JCE [6]
- 3. Enabling Kerberos on Ambari [7]
- 4. Cluster Component Configuration Updates [8]

1.1. Installing and Configuring the KDC

Ambari is able to configure Kerberos in the cluster to work with an existing MIT KDC, or existing Active Directory installation. This section describes the steps necessary to prepare for this integration.



Note

If you do not have an existing KDC (MIT or Active Directory), Install a new MIT KDC. Installing a KDC on a cluster host *after* installing the Kerberos client may overwrite the krb5.conf file generated by Ambari.

You can choose to have Ambari connect to the KDC and automatically create the necessary Service and Ambari principals, generate and distribute the keytabs ("Automated Kerberos Setup"). Ambari also provides an advanced option to manually configure Kerberos. If you choose this option, you must create the principals, generate and distribute the keytabs. Ambari will not do this automatically ("Manual Kerberos Setup").

- Use an Existing MIT KDC [1]
- Use an Existing Active Directory [2]
- Use Manual Kerberos Setup [2]

For convenience, use the instructions to (Optional) Install a new MIT KDC if you do not have an existing KDC available.

1.1.1. Use an Existing MIT KDC

To use an existing MIT KDC for the cluster, you must prepare the following:

- Ambari Server and cluster hosts have network access to both the KDC and KDC admin hosts.
- KDC administrative credentials are on-hand.



Note

You will be prompted to enter the KDC Admin Account credentials during the Kerberos setup so that Ambari can contact the KDC and perform the necessary

principal and keytab generation. By default, Ambari will not retain the KDC credentials unless you have configured Ambari for encrypted passwords.

1.1.2. Use an Existing Active Directory

To use an existing Active Directory domain for the cluster with Automated Kerberos Setup, you must prepare the following:

- Ambari Server and cluster hosts have network access to, and be able to resolve the DNS names of, the Domain Controllers.
- Active Directory secure LDAP (LDAPS) connectivity has been configured.
- Active Directory User container for principals has been created and is on-hand. For example, "OU=Hadoop,OU=People,dc=apache,dc=org"
- Active Directory administrative credentials with delegated control of "Create, delete, and manage user accounts" on the previously mentioned User container are on-hand.



Note

You will be prompted to enter the KDC Admin Account credentials during the Kerberos setup so that Ambari can contact the KDC and perform the necessary principal and keytab generation. By default, Ambari will not retain the KDC credentials unless you have configured Ambari for encrypted passwords.



Note

If Centrify is installed and and being used on any of the servers in the cluster, it is critical that you refer to Centrify's integration guide before attempting to enable Kerberos Security on your cluster. The documentation can be found in the Centrify Server Suite documentation library, with a direct link to the Hortonworks specific PDF here.

1.1.3. Use Manual Kerberos Setup

To perform Manual Kerberos Setup, you must prepare the following:

- Cluster hosts have network access to the KDC.
- Kerberos client utilities (such as kinit) have been installed on every cluster host.
- The Java Cryptography Extensions (JCE) have been setup on the Ambari Server host and all hosts in the cluster.
- The Service and Ambari Principals will be manually created in the KDC before completing this wizard.
- The keytabs for the Service and Ambari Principals will be manually created and distributed to cluster hosts before completing this wizard.

1.1.4. (Optional) Install a new MIT KDC

The following gives a very high level description of the KDC installation process. To get more information see specific Operating Systems documentation, such as RHEL documentation, CentOS documentation, or SLES documentation.



Note

Because Kerberos is a time-sensitive protocol, all hosts in the realm must be time-synchronized, for example, by using the Network Time Protocol (NTP). If the local system time of a client differs from that of the KDC by as little as 5 minutes (the default), the client will not be able to authenticate.

Install the KDC Server

1. Install a new version of the KDC server:

RHEL/CentOS/Oracle Linux

yum install krb5-server krb5-libs krb5-workstation

SLES

zypper install krb5 krb5-server krb5-client

Ubuntu/Debian

apt-get install krb5-kdc krb5-admin-server

2. Using a text editor, open the KDC server configuration file, located by default here:

```
vi /etc/krb5.conf
```

3. Change the [realms] section of this file by replacing the default "kerberos.example.com" setting for the kdc and admin_server properties with the Fully Qualified Domain Name of the KDC server host. In the following example, "kerberos.example.com" has been replaced with "my.kdc.server".

```
[realms]
EXAMPLE.COM = {
   kdc = my.kdc.server
   admin_server = my.kdc.server
```

4. Some components such as HUE require renewable tickets. To configure MIT KDC to support them, ensure the following settings are specified in the libdefaults section of the /etc/krb5.conf file.

```
renew_lifetime = 7d
```



Note

For Ubuntu/Debian, the setup of the default realm for the KDC and KDC Admin hostnames is performed during the KDC server install. You can re-run

setup using dpkg-reconfigure krb5-kdc. Therefore, Steps 2 and 3 above are not needed for Ubuntu/Debian.

Create the Kerberos Database

• Use the utility kdb5_util to create the Kerberos database.

RHEL/CentOS/Oracle Linux

```
kdb5_util create -s
```

SLES

kdb5_util create -s

Ubuntu/Debian

krb5_newrealm

Start the KDC

• Start the KDC server and the KDC admin server.

RHEL/CentOS/Oracle Linux 6

/etc/rc.d/init.d/krb5kdc start

/etc/rc.d/init.d/kadmin start

RHEL/CentOS/Oracle Linux 7

systemctl start krb5kdc

systemctl start kadmin

SLES

rckrb5kdc start

rckadmind start

Ubuntu/Debian

service krb5-kdc restart

service krb5-admin-server restart



Important

When installing and managing your own MIT KDC, it is *very important* to *set up the KDC server to auto-start on boot*. For example:

RHEL/CentOS/Oracle Linux 6

chkconfig kadmin on

RHEL/CentOS/Oracle Linux 7

systemctl enable krb5kdc

systemctl enable kadmin

SLES

chkconfig rckrb5kdc on

chkconfig rckadmind on

Create a Kerberos Admin

Kerberos principals can be created either on the KDC machine itself or through the network, using an "admin" principal. The following instructions assume you are using the KDC machine and using the kadmin.local command line administration utility. Using kadmin.local on the KDC machine allows you to create principals without needing to create a separate "admin" principal before you start.



Note

You will need to provide these admin account credentials to Ambari when enabling Kerberos. This allows Ambari to connect to the KDC, create the cluster principals and generate the keytabs.

1. Create a KDC admin by creating an admin principal.

kadmin.local -q "addprinc admin/admin"

2. Confirm that this admin principal has permissions in the KDC ACL. Using a text editor, open the KDC ACL file:

RHEL/CentOS/Oracle Linux

vi /var/kerberos/krb5kdc/kadm5.acl

SLES

vi /var/lib/kerberos/krb5kdc/kadm5.acl

Ubuntu/Debian

- vi /etc/krb5kdc/kadm5.acl
- 3. Ensure that the KDC ACL file includes an entry so to allow the admin principal to administer the KDC for your specific realm. When using a realm that is different than EXAMPLE.COM, **be sure there is an entry for the realm you are using**. If not present, principal creation will fail. For example, for an admin/admin@HADOOP.COM principal, you should have an entry:

*/admin@HADOOP.COM *

4. After editing and saving the kadm5.acl file, you must restart the kadmin process.

RHEL/CentOS/Oracle Linux 6

/etc/rc.d/init.d/kadmin restart

RHEL/CentOS/Oracle Linux 7

systemctl restart kadmin

SLES

rckadmind restart

Ubuntu/Debian

service krb5-admin-server restart

1.2. Installing the JCE

Before enabling Kerberos in the cluster, you must deploy the Java Cryptography Extension (JCE) security policy files on the Ambari Server and on all hosts in the cluster.



Important

If you are using Oracle JDK, **you must** distribute and install the JCE on all hosts in the cluster, including the Ambari Server. **Be sure to restart Ambari Server after installng the JCE**. If you are using OpenJDK, some distributions of the OpenJDK come with unlimited strength JCE automatically and therefore, installation of JCE is not required.

1.2.1. Install the JCE

- 1. On the Ambari Server, obtain the JCE policy file appropriate for the JDK version in your cluster.
 - For Oracle JDK 1.8:

http://www.oracle.com/technetwork/java/javase/downloads/jce8-download-2133166.html

• For Oracle JDK 1.7:

http://www.oracle.com/technetwork/java/javase/downloads/jce-7-download-432124.html

- 2. Save the policy file archive in a temporary location.
- 3. On Ambari Server and on each host in the cluster, add the unlimited security policy JCE jars to \$JAVA_HOME/jre/lib/security/.

For example, run the following to extract the policy jars into the JDK installed on your host:

unzip -o -j -q jce_policy-8.zip -d /usr/jdk64/jdk1.8.0_60/jre/lib/security/

4. Restart Ambari Server.

1.3. Enabling Kerberos on Ambari

Once you have completed the prerequisites, you are ready to enable Kerberos for Ambari.

1. From the Ambari UI, click Admin, and select Kerberos.

Dashboard	Services	Hosts	Alerts	Admin	=	🛓 admin 🗸
				Stack and	Versions	s
				Service A	ccounts	
				Kerberos	-	<u></u>

- 2. Click Enable Kerberos to launch the Enable Kerberos Wizard.
- 3. From the **Get Started** screen, select the type of KDC you want to use.
- 4. Provide information about the KDC and admin account.
 - a. In the **KDC** section, enter the following information:
 - In the **KDC Host** field, the IP address or FQDN for the KDC host. Optionally a port number may be included.
 - In the **Realm name** field, the default realm to use when creating service principals.
 - (Optional) In the **Domains** field, provide a list of patterns to use to map hosts in the cluster to the appropriate realm. For example, if your hosts have a common domain in their FQDN such as host1.hortonworks.local and host2.hortonworks.local, you would set this to:

.hortonworks.local,hortonworks.local

- b. In the Kadmin section, enter the following information:
 - In the **Kadmin Host** field, the IP address or FQDN for the KDC administrative host. Optionally a port number may be included.
 - The **Admin principal** and **password** that will be used to create principals and keytabs.
 - (Optional) If you have configured Ambari for encrypted passwords, the **Save Admin Credentials** option will be enabled. With this option, you can have Ambari store the KDC Admin credentials to use when making cluster changes.

- 5. From the **Install and Test Kerberos Client** page, proceed with the install. Click **Next** when complete.
- 6. From the **Configure Identities** page, you can customize the Kerberos identities as needed, and proceed to kerberize the cluster.

Be sure to review the principal names, particularly the **Ambari Principals** on the **General** tab. These principal names, by default, append the name of the cluster to each of the Ambari principals. You can leave this as default or adjust these by removing the "-\${cluster-name}" from principal name string.

Click the **Advanced** tab to review the principals and keytabs for each service.

7. Confirm your configurations, and click next to proceed kerberizing your cluster.

I ENABLE KERBEROS WZARD	Kerberize Cluster		
Get Started	Please wait while cluster is being kerberized.		
Configure Kerberos	Preserve man entities crusteler in source were unterconst.		
Install and Test Kerberos Client	Preparing Operations		
Configure Identities	Create Principals 35%		
Confirm Configuration	Create Keytabs		
Stop Services	Configure Ambari Identity		
Kerberize Cluster			
Start and Test Services	Distribute Keytabs		
	Digital Configurations		
	C Finalize Operations		
	+- Back	Next-+	

1.4. Cluster Component Configuration Updates

After you have enabled Kerberos, some cluster components require additional configuration updates.

Storm Configuration Changes

After kerborizing your cluster in Ambari, select the Storm Service, then Configs.

Replace the nimbus.impersonation.acl text:

{ {{storm_bare_jaas_principal}} : {hosts: ['*'], groups: ['*']}}

With this text:

```
{ {{storm_bare_jaas_principal}} : {hosts: ['*'], groups: ['*']},
streamline-$REPLACE_WITH_YOUR_CLUSTER_NAME_LOWER_CASE :
{hosts: ['*'], groups: ['*']}}
```

Enable Kerberos Wizard

Example

If your cluster name is STREAMANALYTICS, the updated nimbus.impersonation.acl is:

```
{ {{storm_bare_jaas_principal}} : {hosts: ['*'], groups: ['*']},
streamline-streamanalytics :
{hosts: ['*'], groups: ['*']}}
```

After make this change, restart Storm. Then go into any Service Pools that are using this storm cluster and referesh them.

Druid Configuration Changes

Update the Druid property druid.hadoop.security.spnego.excludedPaths to the following value:

["/status", "/druid/worker/v1", "/druid/indexer/v1"]

HDFS Configuration Changes

If you are going to use the HDFS processor in your application in secure mode, add the following properties in the HDFS service under custom core-site.xml.

Property Name	Value
hadoop.proxyuser. \$principal_you_configured_in_sam_app_settings.groups	*
hadoop.proxyuser. \$principal_you_configured_in_sam_app_settings.hosts	*

Example

In SAM, you have configured the following principal and keytab under Application Settings:

Application Configuration	×
GENERAL SECURITY ADVANCED	
Clusters Security Config +	
CLUSTER NAME *	Û
streamanalytics	•
PRINCIPAL *	
storm-streamanalytics@STREAMANALYTICS	-
KEYTAB PATH *	
/etc/security/keytabs/storm.headless.keytab	-

The configuration for the 2 HDF properties is:

```
hadoop.proxyuser.storm-streamanalytics.hosts=*
hadoop.proxyuser.storm-streamanalytics.groups=*
```

HBase Configuration

In the HBase service, under custom hbase-site.xml add the following properties

- hbase.thrift.support.proxyuser=true
- hbase.regionserver.thrift.http=true

In HDFS service, add the following under custom core-site.xm

- hadoop.proxyuser.streamline-streamanalytics.hosts=*
- hadoop.proxyuser.streamline-streamanalytics.groups=*

2. NiFi Authentication

After you have installed Ambari and the HDF stack, you have a 2 options for enabling SSL for your NiFi services.

- Enabling SSL with a NiFi Certificate Authority [12]
- Enabling SSL with Existing Certificates [13]

You can use the NiFi service Configs tab Advanced nifi-ambari-ssl-config dialog to configure security for these options.

To access the NiFi SSL configuration dialog:

- 1. From the Ambari services column, click NiFi.
- 2. Click the Configs tabs.
- 3. Click Advanced nifi-ambari-ssl-config.

 Advanced nifi-ambari-s 	sl-config						
Initial Admin Identity	CN=hdf-qe-docs-1.openstacklocal, O	U=HORTONWORKS	•	5			
Enable SSL?	♂ ○ ⊂						
Key password	Type password	Retype Password					
Keystore path	{{nifi_config_dir}}/keystore.jks		•	c			
Keystore password	Type password						
Keystore type			•				
Clients need to authenticate?	• • •						
Truststore path	{{nifi_config_dir}}/truststore.jks		•	c			
Truststore password	Type password	Retype Password					
Truststore type			•				
NIFI CA DN prefix	CN=		•	с			
NIFI CA DN suffix	, OU=HORTONWORKS		•	с			
NiFi CA Certificate Duration	1095						
NiFi Certificate Authority port	10443		•	c			
NiFi CA Force Regenerate?	0 • C						
NiFi CA Token							
Node Identities		I) of each node when clustered (see tool tip for de specified when Ranger <u>Nif</u> plugin will not be used					
	<property name="Node Identity 1">CI OU=HORTONWORKS</property> <property name="Node Identity 2">CI OU=HORTONWORKS</property> <property name="Node Identity 3">CI OU=HORTONWORKS</property>	N=hdf-ge-doca-2.openstacklocal.			0	D	c

2.1. Enabling SSL with a NiFi Certificate Authority

When you enable SSL with the NiFi Certificate Authority (CA) installed, the NiFi CA generates new client certificates for you through Ambari. If you want to enable SSL with a NiFi CA installed, and are planning to use Ranger to manage authorization:

- 1. Select the Enable SSL? box.
- 2. Specify the **NiFi CA** token.

If you want to enable SSL with a NiFi CA installed, and are not yet using Ranger to manage authorization:

- 1. Check the Enable SSL? box.
- 2. Specify the NiFi CA Token.
- 3. Verify that the authorizations.xml file on each node does not contain policies. The authorizations.xml is located in {nifi_internal_dir}/conf. By default, this location is /var/lib/nifi/conf/, and the value of {nifi_internal_dir} is specified in the NiFi internal dir field under Advanced nifi-ambari-config.



Note

If authorizations.xml does contain policies, you must delete it from each node. If you do not, your Initial Admin Identity and Node Identities changes do not take effect.

4. Specify the **Initial Admin Identity**. The **Initial Admin Identity** is the identity of an initial administrator and is granted access to the UI and has the ability to create additional users, groups, and policies. **This is a required value** when you are not using the Ranger plugin for NiFi for authorization.

The Initial Admin Identity format is CN=admin, OU=NIFI.

After you have added the **Initial Admin Identity**, you must immediately generate certificate for this user.

5. Specify the **Node Identities**. This indicates the identity of each node in a NiFi cluster and allows clustered nodes to communicate. **This is a required value** when you are not using the Ranger plugin for NiFi for authorization.

<property name="Node Identity 1">CN=node1.fqdn, OU=NIFI</property> <property name="Node Identity 2">CN=node2.fqdn, OU=NIFI</property> <property name="Node Identity 3">CN=node3.fqdn, OU=NIFI</property>

Replace node1.fqdn, node2.fqdn, and node3.fqdn with their respective fully qualified domain names.

2.2. Enabling SSL with Existing Certificates

If you want to enable SSL with existing certificates, and plan to use Ranger for authorization:

- 1. Check the **Enable SSL?** box.
- 2. Set Keystore path, Keystore password, and Keystore type values.

The keystore path is similar to: /etc/security/nifi-certs/keystore.jks

3. Set the Truststore path, Truststore password, and Truststore type values.

The truststore path is similar to: /etc/security/nifi-certs/truststore.jks

4. Check **Clients need to authenticate?** if you want to ensure that nodes in the cluster are authenticated and are required to have certificates that are trusted by the truststores.

If you want to enable SSL with existing certificates, and are not yet using Ranger for authorization:

- 1. Check the **Enable SSL?** box.
- 2. Set Keystore path, Keystore password, and Keystore type values.

The keystore path is similar to: /etc/security/nifi-certs/keystore.jks

3. Set the Truststore path, Truststore password, and Truststore type values.

The truststore path is similar to: /etc/security/nifi-certs/truststore.jks

- 4. Check **Clients need to authenticate?** to ensure that nodes in the cluster are authenticated and are required to have certificates that are trusted by the Truststores.
- 5. Specify the **Initial Admin Identity**. The **Initial Admin Identity** is the identity of an initial administrator and is granted access to the UI and has the ability to create additional users, groups, and policies. **This is a required value** when you are not using the Ranger plugin for NiFi for authorization.

The Initial Admin Identity format is CN=admin, OU=NIFI.

After you have added the **Initial Admin Identity**, you must immediately generate certificate for this user.

6. Specify the **Node Identities**. This indicates the identity of each node in a NiFi cluster and allows clustered nodes to communicate. **This is a required value** when you are not using the Ranger plugin for NiFi for authorization.

<property name="Node Identity 1">CN=node1.fqdn, OU=NIFI</property> <property name="Node Identity 2">CN=node2.fqdn, OU=NIFI</property> <property name="Node Identity 3">CN=node3.fqdn, OU=NIFI</property>

Replace node1.fqdn, node2.fqdn, and node3.fqdn with their respective fully qualified domain names.

2.3. (Optional) Setting Up Identity Mapping

About This Task

You can use identity mapping properties to normalize user identities. Once you set up identity mapping, NiFi treats identities authenticated by different identity providers (certificates, LDAP, Kerberos) the same. This allows you to avoid creating duplicate users. Additionally, you only need to set up user-specific configurations such as authorizations once per user.

Steps

- 1. From the NiFi service **Configs** tab, click **Advanced nifi-properties**.
- 2. Use the Filter box to search for nifi.security.identity.mapping.pattern.
- 3. Enter the following values:

Table 2.1. Identity mapping values

Field	Sample value
nifi.security.identity.mapping.pattern.dn	^CN=(.*?), OU=(.*?)\$
nifi.security.identity.mapping.value.dn	\$1@\$2
nifi.security.identity.mapping.pattern.kerb	^(.*?)/instance@(.*?)\$
nifi.security.identity.mapping.value.kerb	\$1@\$2

4. Click Save.

5. Restart NiFi using the Restart all Required option from the Action menu.

Example

The following examples demonstrate normalizing DNs from certificates and principals from Kerberos:

```
nifi.security.identity.mapping.pattern.dn=^CN=(.*?), OU=(.*?), O=(.*?), L=(.*?), ST=(.*?), C=(.*?)$
nifi.security.identity.mapping.value.dn=$1@$2
nifi.security.identity.mapping.pattern.kerb=^(.*?)/instance@(.*?)$
nifi.security.identity.mapping.value.kerb=$1@$2
```

2.4. Generating Client Certificates

If you are using a CA, you can use the TLS Toolkit provided in the HDF management pack to generate the required client certificates so that you can log into NiFi after enabling SSL.

1. Navigate the TLS Toolkit directory, which will be similar to:

```
cd /var/lib/ambari-agent/cache/common-services/NIFI/1.0.0/package/files/
nifi-toolkit-$version
```

For example:

```
cd /var/lib/ambari-agent/cache/common-services/NIFI/1.0.0/package/files/
nifi-toolkit-1.1.0.2.1.3.0-6
```

2. From the command line, run the following:

```
bin/tls-toolkit.sh client
-c <CA host name>
-D "<distinguished name>"
-p <CA host port>
-t <NiFi CA token>
-T <keystore type>
```

Your command should look similar to:

```
bin/tls-toolkit.sh client
-c nifi.cert.authority.example.com
-D "CN=admin, OU=NIFI"
-t nifi
-p 10443
-T pkcs12
```

3. To get your keystore password, enter:

cat config.json

- 4. Verify that the installation directory contains the following two files:
 - keystore.pkcs12
 - nifi-cert.pem
- 5. To double-click your keystore file to launch your OS certificate management application, change keystore.pkcs12 to keystore.p12.
- 6. Import the nifi-cert.pem file as your trusted CA.
- 7. Import keystore.pkcs12 as the client certificate.

Re-running the TLS Toolkit generates a new set of keystore and configuration files. To avoid having your files overwritten, save the keystore and configuration files to an alternate location before re-running the TLS Toolkit.

For more information about the TLS Toolkit, see TLS Generation Toolkit in the *Administration Guide*.

2.5. Logging into NiFi After Enabling SSL

Now that you have set up SSL, you need to enable logging into NiFi with a certificate:

- 1. Launch NiFi from the Ambari Quick Links menu.
- 2. Select the certificate you just imported from the browser prompt.
- 3. Log in with the user name and password you created during installation.



Note

When you are running NiFi on a host with Ambari and with SSL enabled, the default URL becomes secured https://<local-host>:9091/nifi.

3. SAM Authentication

After you Kerborize the cluster and try to access the SAM UI for the first time, an Authentication Required message displays. To log into SAM for the first time and to create other users, you must log in with the streamline principal and keytab. Ambari creates the streamline principal and keytab during the Kerberos process.

Details of the principal and the keyab:

- The ketab is called streamline.service.keytab and islocated on the node where SAM is installed. It is located under /etc/security.
- The principal name has the following convention: streamline-<cluster_name_lower_case>

After you have logged into SAM as the streamline user, you can create other users

3.1. Logging into SAM for the First Time

About This Task

To log into SAM for the first time and to create other users, you must log in with the streamline principal and keytab.

Steps

- 1. Use Ambari to download the Kerboros client your local machine:
 - a. In Ambari, select Hosts, and select a host.
 - b. Click Host Actions, then Download Client Configs, then Kerberos Client.
 - c. Run the following command:

tar -zxvf KERBEROS_CLIENT-configs.tar

- d. Copy the krb5.conf to /etc.
- 2. Copy the Keytab for the streamline user.

Copy the key tab from \$FQDN_SAM_NODE:/etc/security/keytabs/
streamline.service.keytab to you local machine.

3. Log in as the streamline user:

```
kinit -kt streamline.service.keytab streamline-
<your_cluster_name>@<REALM_NAME>
```

Result

You are now able to access the SAM UI securely, and can proceed with creating additional users.

More Information

See Managing Users and Assigning them to Roles

3.2. Logging In as a Different User

If you want to log in as one of the users you have created, enter:

kinit <user-name>@<REALM_NAME>

Example

After the user solson is created, to log in as that user, perform a kinit as solson. After successful kinit, when the user solson goes to the SAM UI, they see the following:

5	Configuration / Authorizer		
ħ	USERS ROLES		
43 90 (b)	solson	roles 1	NAME *
¢	streamline-streamanalytics	roles 1	EMAIL *
r	gvetticaden	ROLES 1	ROLES
	harsha	ROLES 1	× ROLE_ADMIN
	suresh	ROLES 1	Service Pool
	guru	ROLES 1	Environments
	dan	ROLES 1	SAVE CANCEL

4. Installing Ranger

Apache Ranger can be installed either manually or using the Ambari UI. Unlike the manual installation process, which requires you to perform a number of installation steps, installing Ranger using the Ambari UI is simpler and easier. Once Ambari has been installed and configured, you can use the **Add Service** wizard to install the following components:

- Ranger Admin
- Ranger UserSync
- Ranger Key Management Service

4.1. Ranger Installation Prerequisites

Before you install Ranger, make sure your cluster meets the following requirements:

- You have installed Log Search or have an external Solr running.
- A MySQL, Oracle, or PostgreSQL database instance must be running and available to be used by Ranger. Configuration of the database instance for Ranger is described in the following sections for some of the databases supported by Ranger.
 - Configuring MySQL for Ranger [19]
 - Configuring PostgreSQL for Ranger [21]
 - Configuring Oracle for Ranger [22]
- If you choose not to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the dba_script.py Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. You can then run the normal Ambari Ranger installation without specifying a DBA user name and password. For more information see Setting up Database Users Without Sharing DBA Credentials.
- The Ranger installation creates two new users (default names: rangeradmin and rangerlogger) and two new databases (default names: ranger and ranger_audit).

4.2. Setting up Databases for Ranger

- Configuring MySQL for Ranger [19]
- Configuring PostgreSQL for Ranger [21]
- Configuring Oracle for Ranger [22]

4.2.1. Configuring MySQL for Ranger

1. The MySQL database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the rangerdba user with password rangerdba.

a. Log in as the root user, then use the following commands to create the rangerdba user and grant it adequate privileges.

```
CREATE USER 'rangerdba'@'localhost' IDENTIFIED BY 'rangerdba';
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'localhost';
CREATE USER 'rangerdba'@'%' IDENTIFIED BY 'rangerdba';
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'%';
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'localhost' WITH GRANT OPTION;
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'%' WITH GRANT OPTION;
FLUSH PRIVILEGES;
```

- b. Use the exit command to exit MySQL.
- c. You should now be able to reconnect to the database as rangerdba using the following command:

mysql -u rangerdba -prangerdba

After testing the rangerdba login, use the exit command to exit MySQL.

2. Use the following command to confirm that the mysql-connector-java.jar file is in the Java share directory. This command must be run on the server where Ambari server is installed.

```
ls /usr/share/java/mysql-connector-java.jar
```

If the file is not in the Java share directory, use the following command to install the MySQL connector .jar file.

RHEL/CentOS/Oracle Linux

yum install mysql-connector-java*

SLES

zypper install mysql-connector-java*

3. Use the following command format to set the jdbc/driver/path based on the location of the MySQL JDBC driver .jar file.This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/
path}
```

For example:

```
ambari-server setup --jdbc-db=mysql --jdbc-driver=/usr/share/java/mysql-
connector-java.jar
```

4.2.2. Configuring PostgreSQL for Ranger

1. On the PostgreSQL host, install the applicable PostgreSQL connector.

RHEL/CentOS/Oracle Linux

yum install postgresql-jdbc*

SLES

zypper install -y postgresql-jdbc

2. Confirm that the .jar file is in the Java share directory.

ls /usr/share/java/postgresql-jdbc.jar

3. Change the access mode of the .jar file to 644.

chmod 644 /usr/share/java/postgresql-jdbc.jar

4. The PostgreSQL database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the rangerdba user and grant it adequate privileges.

```
echo "CREATE DATABASE $dbname;" | sudo -u $postgres psql -U $postgres
echo "CREATE USER $rangerdba WITH PASSWORD '$passwd';" | sudo -u $postgres
psql -U $postgres
echo "GRANT ALL PRIVILEGES ON DATABASE $dbname TO $rangerdba;" | sudo -u
$postgres psql -U $postgres
```

Where:

- \$postgres is the Postgres user.
- \$dbname is the name of your PostgreSQL database
- \$passwd is the password for your Ranger Admin user
- \$rangerdba is the username for your Ranger Admin user
- 5. Use the following command format to set the jdbc/driver/path based on the location of the PostgreSQL JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/
path}
```

For example:

```
ambari-server setup --jdbc-db=postgres --jdbc-driver=/usr/share/java/
postgresql-jdbc.jar
```

6. Run the following command:

export HADOOP_CLASSPATH=\${HADOOP_CLASSPATH}:\${JAVA_JDBC_LIBS}:/connector jar path

- 7. Add Allow Access details for Ranger users:
 - (Optional) Use the following command to find the location of <code>postgresql.conf</code> and <code>pg_hba.conf</code>:

echo "SHOW config_file;" | sudo -u \$postgres psql -U \$postgres

- change listen_addresses='localhost' to listen_addresses='*' ('*'
 any) to listen from all IPs in postgresql.conf.
- Add the Ranger Admin user to the appropriate line in the $\tt pg_hba.conf$ file, the following provides an example:

# TYPE	DATABASE	USER	CIDR-ADDRESS	METHOD	
local # IPv4 <mark>h</mark> ost # IPv6	all po local conne all po local conne	stgres,ran ctions: stgres,ran ctions:	n socket connections on ngeradmin,rangerlogger ngeradmin,rangerlogger	trust 0.0.0.0/0	trust
			ngeradmin,rangerlogger .conf" 74L, 3445C	::/0	trust

8. After editing the pg_hba.conf file, run the following command to refresh the PostgreSQL database configuration:

sudo -u postgres /usr/bin/pg_ctl -D \$PGDATA reload

For example, if the pg_hba.conf file is located in the /var/lib/pgsql/data directory, the value of \$PGDATA is /var/lib/pgsql/data.

4.2.3. Configuring Oracle for Ranger

- 1. On the Oracle host, install the appropriate JDBC .jar file.
 - Download the Oracle JDBC (OJDBC) driver from http://www.oracle.com/ technetwork/database/features/jdbc/index-091264.html.
 - For Oracle Database 11g: select Oracle Database 11g Release 2 drivers > ojdbc6.jar.
 - For Oracle Database 12c: select Oracle Database 12c Release 1 driver > ojdbc7.jar.
 - Copy the .jar file to the Java share directory. For example:

cp ojdbc7.jar /usr/share/java



Note

Make sure the .jar file has the appropriate permissions. For example:

chmod 644 /usr/share/java/ojdbc7.jar

2. The Oracle database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the RANGERDBA user and grant it permissions using SQL*Plus, the Oracle database administration utility:

```
# sqlplus sys/root as sysdba
CREATE USER $RANGERDBA IDENTIFIED BY $RANGERDBAPASSWORD;
GRANT SELECT_CATALOG_ROLE TO $RANGERDBA;
GRANT CONNECT, RESOURCE TO $RANGERDBA;
QUIT;
```

3. Use the following command format to set the jdbc/driver/path based on the location of the Oracle JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/
path}
```

For example:

```
ambari-server setup --jdbc-db=oracle --jdbc-driver=/usr/share/java/ojdbc6.
jar
```

4.3. Installing Ranger

To install Ranger using Ambari:

- 1. Start the Installation [
- 2. Customize Services [26]
- 3. Complete the Ranger Installation [50]

Related Topics


• Setting up Database Users Without Sharing DBA Credentials [54]

1

• Updating Ranger Admin Passwords [55]

4.3.1. Start the Installation

- 1. Log into your Ambari cluster with your designated user credentials. The main Ambari Dashboard page will be displayed.
- 2. From the main Ambari Dashboard page, click Actions, then select Add Service.



3. On the Choose Services page, select Ranger, then click Next.

Add Service Wizard

ADD SERVICE WIZARD Choose Services	Choose Se	rvices	
Assign Masters	Choose which services	you want to insta	all on your cluster.
Assign Slaves and Clients Customize Services	⊯ Service	Version	Description
Configure Identities	ZooKeeper	3.4.6.2.0	Centralized service which provides highly reliable distributed coordination
Review	Storm	1.0.1.2.0	Apache Hadoop Stream processing framework
Install, Start and Test Summary	Z Ambari Infra	0.1.0	Core shared service used by Ambari managed components.
	Ambari Metrics	0.1.0	A system for metrics collection that provides storage and retrieval capability for metrics collected from the cluster
	🗹 Kafka	0.10.0.2.0	A high-throughput distributed messaging system
	☑ Log Search	0.5.0	Log aggregation, analysis, and visualization for Ambari managed services. This service is Technical Preview.
	of Ranger	0.6.0.2.0	Comprehensive security for Hadoop
	⊠ NFI	1.0.0.2.0	Apache NiFi is an easy to use, powerful, and reliable system to process and distribute data.
			Next -+

4. The Ranger Requirements page appears. Ensure that you have met all of the installation requirements, then select the "I have met all the requirements above" check box and click **Proceed**.

 Ranger to access to the database. (Note: This is applicable for only Ranger 0.4.0) 3. Ensure that the access for the DB Admin user is enabled in DB server from any host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: 	 In Assign Masters step of this wizard, you will be prompted to specify which host for the Ranger Admin. On that host, you must have DB Client installed for Ranger to access to the database. (Note: This is applicable for only Ranger 0.4.0) Ensure that the access for the DB Admin user is enabled in DB server from any host. Execute the following command on the Ambari Server host. Replace database. type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/ jdbc/driver/path}
 Ranger to access to the database. (Note: This is applicable for only Ranger 0.4.0) 3. Ensure that the access for the DB Admin user is enabled in DB server from any host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path} 	 Ranger to access to the database. (Note: This is applicable for only Ranger 0.4.0) 3. Ensure that the access for the DB Admin user is enabled in DB server from any host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path}
 0.4.0) 3. Ensure that the access for the DB Admin user is enabled in DB server from any host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path} 	 0.4.0) 3. Ensure that the access for the DB Admin user is enabled in DB server from any host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path}
 Ensure that the access for the DB Admin user is enabled in DB server from any host. Execute the following command on the Ambari Server host. Replace database type with mysql]oracle]postgres]mssql]sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path} 	 3. Ensure that the access for the DB Admin user is enabled in DB server from any host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path}
<pre>host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql]oracle]postgres]mssql]sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/ jdbc/driver/path}</pre>	<pre>host. 4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/ jdbc/driver/path}</pre>
4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path}	4. Execute the following command on the Ambari Server host. Replace database type with mysql oracle postgres mssql sqlanywhere and /jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path}
<pre>/jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/ jdbc/driver/path}</pre>	<pre>/jdbc/driver/path based on the location of corresponding JDBC driver: ambari-server setupjdbc-db={database-type}jdbc-driver={/ jdbc/driver/path}</pre>
ambari-server setupjdbc-db={database-type}jdbc-driver={/jdbc/driver/path}	<pre>ambari-server setupjdbc-db={database-type}jdbc-driver={/ jdbc/driver/path}</pre>
jdbc/driver/path}	jdbc/driver/path}
jdbc/driver/path}	jdbc/driver/path}
I have met all the requirements above.	I have met all the requirements above.
I have met all the requirements above.	I have met all the requirements above.

5. From the **Assign Masters** page, you are then prompted to select the host where you want to install Ranger Admin. This host must have DB admin access to the Ranger DB host and User Sync.

Make a note of the Ranger Admin host for use in subsequent installation steps. Click **Next** when finished to continue with the installation.



Note

The Ranger Admin and Ranger User Sync services must be installed on the same cluster node.

Add Service Wizard			
	UTI U URITO.	module on the needs with even a	
	Infra Solr Instance:	abajwa-hdf-qe-docs-1.openstack \$	abajwa-hdf-qe-docs-3.openstacklocal (15.6 GB, 2 cores)
	Grafana:	abajwa-hdf-qe-docs-1.openstack \$	ZooKeeper Server Metrics Collector
	Metrics Collector:	abajwa-hdf-qa-docs-3.openstack \$	Ranger Admin Ranger Usersync NJ/1
	Kafka Broker:	abajwa-hdf-qe-docs-1.openstack \$	
	Log Search Server:	abajwa-hdf-qe-docs-1.openstack \$	
	Ranger Admin:	abajwa-hdf-qa-docs-3.openstack \$	
	Ranger Usersync:	abajwa-hdf-qe-docs-3.openstack \$	
	NFL	abajwa-hdf-qe-docs-2.openstac# \$	•
	NFC	abajwa-hdf-qe-docs-3.openstack \$	
	NIFE	abajwa-hdf-qe-docs-1.openstack \$	

- 6. From the Assign Slaves and Clients page, click Next.
- 7. The Customize Services page appears. These settings are described in the next section.

4.3.2. Customize Services

The next step in the installation process is to specify Ranger settings on the Customize Services page.

- Ranger Admin Settings [26]
- Configure Ranger User Sync [35]
- Specify Plugins to Enable [41]
- Ranger Audit Settings [42]
- Configure Ranger Authentication [43]

4.3.2.1. Ranger Admin Settings

1. On the Customize Services page, select the Ranger Admin tab, then use the **DB Flavor** drop-down to select the database type that you are using with Ranger.

Add Service Wizard

ADD SERVICE WIZARD Choose Services	Customize Services		
Assign Masters Assign Slaves and Clients	We have come up with recommended configurations	for the services you selected. Customize them as you see fit	
Customize Services Configure Identities	ZooKeeper Storm Ambari Infra Ambari Metrics	Kafka Log Search Ranger (1) NIFI Misc	
Review	There are 3 configuration changes in 3 services Show	Details	
Install, Start and Test			
Summary	Group Default (3) Manage Config Groups	Filter	•
		gin Ranger Audit 🚺 Ranger Tagsync Advanced	
	DB FLAVOR MYSQL	A Ranger DB host	`
	Ranger DB name ranger	Driver class name for a JDBC Ranger database com.mysql.jdbc.Driver	

2. Enter the database server address in the Ranger DB Host box.

DB Flavor	Host	Example
MySQL	<host[:port]></host[:port]>	c6401.ambari.apache.org
		or
		c6401.ambari.apache.org:3306
Oracle	<host:port:sid></host:port:sid>	c6401.ambari.apache.org:1521:ORCL
	<host:port service=""></host:port>	c6401.ambari.apache.org:1521/XE
PostgreSQL	<host[:port]></host[:port]>	c6401.ambari.apache.org
		or
		c6401.ambari.apache.org:5432
MS SQL	<host[:port]></host[:port]>	c6401.ambari.apache.org
		or
		c6401.ambari.apache.org:1433
SQLA	<host[:port]></host[:port]>	c6401.ambari.apache.org
		or
		c6401.ambari.apache.org:2638

Table 4.1. Ranger DB Host

3. **Ranger DB name** – The name of the Ranger Policy database, i.e. ranger_db. Please not that if you are using Oracle, you must specify the Oracle tablespace name here.

4. Driver class name for a JDBC Ranger database – the driver class name is automatically generated based on the selected DB Flavor. The table below lists the default driver class settings. Currently Ranger does not support any third party JDBC driver.

Table 4.2. Driver Class Name

DB Flavor	Driver class name for a JDBC Ranger database
MySQL	com.mysql.jdbc.Driver
Oracle	oracle.jdbc.driver.OracleDriver
PostgreSQL	org.postgresql.Driver
MS SQL	com.microsoft.sqlserver.jdbc.SQLServerDriver
SQLA	sap.jdbc4.sqlanywhere.IDriver

5. Ranger DB username and Ranger DB Password – Enter the user name and passwords for your Ranger database server. The following table describes these settings in more detail. You can use the MySQL database that was installed with Ambari, or an external MySQL, Oracle, PostgreSQL, MS SQL or SQL Anywhere database.

Table 4.3. Ranger DB Username Settings

Property	Description	Default Value	Example Value	Required?
Ranger DB username	The username for the Policy database.	rangeradmin	rangeradmin	Yes
Ranger DB password	The password for the Ranger Policy database user.		PassWORd	Yes

6. JDBC connect string



Important

Currently the Ambari installer generates the JDBC connect string using the jdbc:oracle:thin:@//host:port/db_name format. You must replace the connection string as described in the following table:

Table 4.4. JDBC Connect String

DB Flavor	Syntax	Example Value
MySQL	jdbc:mysql://DB_HOST:PORT/ db_name	jdbc:mysql:// c6401.ambari.apache.org:3306/ ranger_db
Oracle	For Oracle SID: jdbc:oracle:thin:@DB_HOST:PORT:SID	jdbc:oracle:thin:@c6401.ambari.apache.org:1521: ORCL
	For Oracle Service Name: jdbc:oracle:thin:@//DB_HOST[:PORT] [/ServiceName]	jdbc:oracle:thin:@// c6401.ambari.apache.org:1521/ XE
PostgreSQL	jdbc:postgresql://DB_HOST/ db_name	jdbc:postgresql:// c6401.ambari.apache.org:5432/ ranger_db
MS SQL	jdbc:sqlserver:// DB_HOST;databaseName=db_name	jdbc:sqlserver:// c6401.ambari.apache.org:1433;databaseName=ranger_db
SQLA	jdbc:sqlanywhere:host=DB_HOST;dat	a ja#se:=qla_nyawhe re:host=c6401.ambari.apache.org:2638;dat

7. Setup Database and Database User

• If set to **Yes** – The Database Administrator (DBA) user name and password will need to be provided as described in the next step.



Note

Ranger does not store the DBA user name and password after setup. Therefore, you can clear these values in the Ambari UI after the Ranger setup is complete.

• If set to No – A No indicates that you do not wish to provide Database Administrator (DBA) account details to the Ambari Ranger installer. Setting this to No continues the Ranger installation process without providing DBA account details. In this case, you must perform the system database user setup as described in Setting up Database Users Without Sharing DBA Credentials, and then proceed with the installation.



Note

If **No** is selected and the UI still requires you to enter a user name and password in order to proceed, you can enter any value – the values do not need to be the actual DBA user name and password.

8. Database Administrator (DBA) username and Database Administrator (DBA) password – The DBA username and password are set when the database server is installed. If you do not have this information, contact the database administrator who installed the database server.

Table 4.5. DBA Credential Settings

Property	Description	Default Value	Example Value	Required?
Database Administrator (DBA) username	The Ranger database user that has administrative privileges to create database schemas and users.	root	root	Yes
Database Administrator (DBA) password	The root password for the Ranger database user.		root	Yes

If the Oracle DB root user Role is SYSDBA, you must also specify that in the **Database Administrator (DBA) username** parameter. For example, if the DBA user name is orcl_root you must specify orcl_root AS SYSDBA.



Note

As mentioned in the note in the previous step, if **Setup Database and Database User** is set to **No**, a placeholder DBA username and password may still be required in order to continue with the Ranger installation.

The following images show examples of the DB settings for each Ranger database type.

Note

To test the DB settings, click **Test Connection**. If a Ranger database has not been pre-installed, **Test Connection** will fail even for a valid configuration.

MySQL

anger Admin Ranger User Info Ranger Plugin R	
Ranger Admin	
DB FLAVOR	Ranger DB host
MYSQL ·	c6402.ambari.apache.org
Ranger DB name	Driver class name for a JDBC Ranger database
ranger	com.mysql.jdbc.Driver
Ranger DB username	Ranger DB password
rangeradmin	····· •
Setup Database and Database User	
Database Administrator (DBA) usemame	Database Administrator (DBA) password
rangerdba	···· •
IDBC connect string for root user	

Oracle – if the Oracle instance is running with a Service name.

Ranger Admin	
DB FLAVOR	Ranger DB host
ORACLE ·	c6402.ambari.apache.org:1521/XE
Ranger DB name	Driver class name for a JDBC Ranger database
ranger	oracle.jdbc.driver.OracleDriver
Ranger DB username	Ranger DB password
rangeradmin	······ •
Setup Database and Database User	
Setup Database and Database User	
Setup Database and Database User Yes	
Setup Database and Database User Yes Database Administrator (DBA) username	Database Administrator (DBA) password
Yes	Database Administrator (DBA) password

Oracle – if the Oracle instance is running with a SID.

Ranger Admin	
DB FLAVOR	Ranger DB host
ORACLE ·	c6402.ambari.apache.org:1521:ORCL
Ranger DB name	Driver class name for a JDBC Ranger database
ranger	oracle.jdbc.driver.OracleDriver
Ranger DB usemame	Ranger DB password
rangeradmin	
jdbc:oracle:thin:@//c6402.ambari.apache.or Setup Database and Database User	
Database Administrator (DBA) username	Database Administrator (DBA) password
	······ ()
rangerdba	
rangerdba JDBC connect string for root user	

PostgreSQL

Ranger Admin	
DB FLAVOR	Ranger DB host
POSTGRES -	c6402.ambari.apache.org:5432
Ranger DB name	Driver class name for a JDBC Ranger database
ranger	org.postgresql.Driver
Ranger DB username	Ranger DB password
rangeradmin	••••••••••••••••••••••••••••••••••••••
Setup Database and Database User	
Setup Database and Database User	
Yes	Database Administrator (DBA) password
	Database Administrator (DBA) password

MS SQL

anger Admin	
3 FLAVOR	Ranger DB host
ISSQL •	c6402.ambari.apache.org:1433
inger DB name	Driver class name for a JDBC Ranger database
inger	com.microsoft.sqlserver.jdbc.SQLServerE
inger DB username	Ranger DB password
angeradmin	••••••
tup Database and Database User	
itabase Administrator (DBA) username	Database Administrator (DBA) password
angerdba	•••••••

SQL Anywhere

Ranger DB host c6402.ambari.apache.org:2638 Driver class name for a JDBC Ranger database	
Driver class name for a JDBC Ranger database	
sap.jdbc4.sqlanywhere.IDriver	
Ranger DB password	
····· (9)	
	0
Database Administrator (DBA) password	
Database Administrator (DBA) password	
	Ranger DB password

4.3.2.2. Configure Ranger User Sync

This section describes how to configure Ranger User Sync for either UNIX or LDAP/AD.

- Configuring Ranger User Sync for UNIX [35]
- Configuring Ranger User Sync for LDAP/AD [36]

4.3.2.2.1. Configuring Ranger User Sync for UNIX

Use the following steps to configure Ranger User Sync for UNIX.

- 1. On the Customize Services page, select the Ranger User Info tab.
- 2. Click **Yes** under Enable User Sync.
- 3. Use the Sync Source drop-down to select UNIX, then set the following properties.

Table 4.6. UNIX User Sync Properties

Property	Description	Default Value
Sync Source	Only sync users above this user ID.	500
Password File	The location of the password file on the Linux server.	/etc/passwd
Group File	The location of the groups file on the Linux server.	/etc/group

Add Service Wizard

Review	There are 6 configuration changes in 4 services Show Details		
Install, Start and Test Summary	Group Default (3) Manage Config Groups	Filter	•
	Ranger Admin Ranger User Info Ranger Plugin Ranger Audit (1)	Ranger Tagsync Advanced	
	Ranger User Info Enable User Sync	`	
	Sync Source		
	Minimum User ID 500		
	Password File /etc/passwd		

4.3.2.2.2. Configuring Ranger User Sync for LDAP/AD

Use the following steps to configure Ranger User Sync for LDAP/AD.

- 1. On the Customize Services page, select the Ranger User Info tab.
- 2. Click **Yes** under Enable User Sync.
- 3. Use the Sync Source drop-down to select LDAP/AD.
- 4. Set the following properties on the Common Configs tab.

Property	Description	Default Value	Sample Values
LDAP/AD URL	Add URL depending upon LDAP/AD sync source	ldap://{host}:{port}	ldap:// ldap.example.com:389 or ldaps:// ldap.example.com:636
Bind Anonymous	If Yes is selected, the Bind User and Bind User Password are not required.	NO	
Bind User	The location of the groups file on the Linux server.	The full distinguished name (DN), including common name (CN), of an LDAP/ AD user account that has privileges to search for users. The LDAP bind DN is used to connect to LDAP and query for users and groups.	cn=admin,dc=example,dc=con or admin@example.com
Bind User Password	The password of the Bind User.		

Table 4.7. LDAP/AD Common Configs

Add Service Wizard		Х
	Group Default (1) Manage Config Groups Filter	
	Ranger Admin Ranger User Info 😢 Ranger Plugin Ranger Audit Ranger Tagsyno Advanced	
	Ranger User Info Enable User Sync	
	Byno Bouroe LDAP/AD	
	Common Configs User Configs D Group Configs	
	LDAPAD URL Idap://172.22.126.189:389	
	Bind Asonymous	
	Bind User	
	cn=Manager,dc=qe,dc=hortonworks,dc=com	
	Bind User Password	
	······································	

5. Set the following properties on the User Configs tab.

Table 4.8. LDAP/AD User Configs

Property	Description	Default Value	Sample Values]
Group User Map Sync	Sync specific groups for users.	Yes	Yes	
Username Attribute	The LDAP user name attribute.		sAMAccountName for AD, uid or cn for OpenLDAP	
User Object Class	Object class to identify user entries.	person	top, person, organizationalPerson, user, or posixAccount	
User Search Base	Search base for users. Ranger can search multiple OUs in AD. Ranger UserSync module performs a user search on each configured OU and adds all the users into single list. Once all the OUs are processed, a user's group membership is computed based on the group search.		cn=users,dc=example,dc=cor	n;ou=example1,ou=e
User Search Filter	Optional additional filter constraining the users selected for syncing.		Sample filter to retrieve all the users: cn=* Sample filter to retrieve all the users who are members of groupA or groupB: ((memberof=CN=GroupA,OU (memberof=CN=GroupB,OU	J=groups,DC=example
User Search Scope	This value is used to limit user search to the depth from search base.	sub	base, one, or sub	
User Group Name Attribute	Attribute from user entry whose values would be treated as group values to be pushed into the Access Manager database. You can provide multiple attribute names separated by commas.	memberof, ismemberof	memberof, ismemberof, or gidNumber	
Enable User Search	This option is available only when the "Enable Group Search First" option is selected.	No	Yes	

Add Service Wizard

Sync Source LDAP/AD			
			o
Common Configs User C	onfigs Group Configs		
Usemame Attribute			
uid			
User Object Class			
person			
User Search Base			
dc=qe;dc=hortonworks;de	c=com		
dc=qe;dc=hortonworks;de	=com		
	=com		
dc=qe;dc=hortonworks;dd User Search Filter	c=com		
	=com		
User Search Filter	=com		
User Search Filter	=com		
User Search Filter	2=COM		
User Search Filter	=com		
User Search Filter	=com		
User Search Filter	2=COM		
User Search Filter	=com		

6. Set the following properties on the Group Configs tab.

Table 4.9. LDAP/AD Group Configs

Property	Description	Default Value	Sample Values
Enable Group Sync	If Enable Group Sync is set to No, the group names the users belong to are derived from "User Group Name Attribute". In this case no additional group filters are applied.		Yes

Property	Description	Default Value	Sample Values	
	If Enable Group Sync is set to Yes, the groups the users belong to are retrieved from LDAP/AD using the following group-related attributes.			-
Group Member Attribute	The LDAP group member attribute name.		member	
Group Name Attribute	The LDAP group name attribute.		distinguishedName for AD, cn for OpenLdap	-
Group Object Class	LDAP Group object class.		group, groupofnames, or posixGroup	
Group Search Base	Search base for groups. Ranger can search multiple OUs in AD. Ranger UserSync module performs a user search on each configured OU and adds all the users into single list. Once all the OUs are processed, a user's group membership is computed based on the group search configuration. Each OU segment needs to be separated by a ; (semi- colon).		ou=groups,DC=example,DC=	tom;ou=group1;ou=
Group Search Filter	Optional additional filter constraining the groups selected for syncing.		Sample filter to retrieve all groups: cn=* Sample filter to retrieve only the groups whose cn is Engineering or Sales: ((cn=Engineering) (cn=Sales))	
Enable Group Search First	 When Enable Group Search First is selected, there are two possible ways of retrieving users: If Enable User Search is not selected: users are retrieved from the "member" attribute of the group. If Enable User Search is selected: user membership is computed by performing an LDAP search based on the user configuration. 	No	Yes	

Add Service Wizard		
	Ranger Admin Ranger User Into Ranger Pugin Ranger Audt Advanced	
	Ranger User Info Enable User Sync	
	Bync Bource LDAPIAD +	o
	Common Configs User Configs Group Configs	
	Enable Group Bync	o
	Group Member Attribute	0
	Group Name Attribute	9
	Group Object Class groupOfNames	0
	Group Search Base do=qe;do=hortonworks;do=com	0
	Group Search Filter	
	ch**	0
	Enable Group Search First	o

4.3.2.3. Specify Plugins to Enable

From the **Ranger Plugin** tab, use the **ON/OFF** slider to indicate which plugins you want to enable. You can also enable plugins at a later time.

If you select the Storm or Kafka plugins here, they are not enabled until you also enable Kerberos.

ssign Slaves and Clients	we have come up with recommence	ed configurations for the services you selecte	o. Customize them as you see in	L
ustomize Services	ZooKeeper Storm Amberi Infra	Ambari Metrics Kafka Log Search	Ranger () NIFI Misc	
onfigure identities eview	There are 12 configuration changes	in 4 services Show Details		
stall, Start and Test				
ummary	Group Default (3) · Manag	e Config Groups	Filter	•
	Ranger Admin Ranger User Info	Ranger Plugin Ranger Audit 🕦 Rang	er Tagsyno Advanced	
	Ranger Plugin			
	NIFI Ranger Plugin	Storm Ranger Plugin	Kafka Ranger Plugin	
	ON	ON	ON	
	_			
	Attention: Some configurations	need your attention before you can proceed.		
	Show me properties with issues			

Add Service Wizard

4.3.2.4. Ranger Audit Settings

Apache Ranger uses Apache Solr to store audit logs and provides UI searching through the audit logs. Solr must be installed and configured before installing Ranger Admin or any of the Ranger component plugins. The default configuration for Ranger Audits to Solr uses the shared Solr instance provided under the Ambari Infra service. Solr is both memory and CPU intensive. If your production system has high volume of access requests, make sure that the Solr host has adequate memory, CPU, and disk space.

SolrCloud is the preferred setup for production usage of Ranger. SolrCloud, which is deployed with the Ambari Infra service, is a scalable architecture that can run as a single node or multi-node cluster. It has additional features such as replication and sharding, which is useful for high availability (HA) and scalability. You should plan your deployment based on your cluster size. Because audit records can grow dramatically, plan to have at least 1 TB of free space in the volume on which Solr will store the index data. Solr works well with a minimum of 32 GB of RAM. You should provide as much memory as possible to the Solr process. It is highly recommended to use SolrCloud with at least two Solr nodes running on different servers with replication enabled. SolrCloud also requires Apache ZooKeeper.

- 1. On the Customize Services page, select the Ranger Audit tab.
- 2. Under Audit to Solr, click **OFF** under SolrCloud to enable SolrCloud. The button label will change to ON, and the SolrCloud configuration settings will be loaded automatically.

Add	Service	Wizard	
-----	---------	--------	--

a controo trizara						
	Ranger Admin	Ranger User Info	Ranger Plugin	Ranger Audit 1	Ranger Tagsync	Advanced
	Audit to S	olr				
	Audit to Solr					
	ON					
	SoliCloud					
	A ranger.audit.ac	oir unia				
	ranger.audit.soir. ranger_soir	usemame				
	ranger.audit.soir;	password				

4.3.2.5. Configure Ranger Authentication

This section describes how to configure Ranger authentication for UNIX, LDAP, and AD.

- Configuring Ranger UNIX Authentication [43]
- Configuring Ranger LDAP Authentication [44]
- Configuring Ranger Active Directory Authentication [47]

4.3.2.5.1. Configuring Ranger UNIX Authentication

Use the following steps to configure Ranger authentication for UNIX.

- 1. Select the Advanced tab on the Customize Services page.
- 2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the External URL box in the format http://<your_ranger_host>:6080.
- 3. Under Ranger Settings, select UNIX.

HTTP is enabled by default – if you disable HTTP, only HTTPS is allowed.

4. Under UNIX Authentication Settings, set the following properties.

Property	Description	Default Value	Example Value
Allow remote Login	Flag to enable/ disable remote login. Only applies to UNIX authentication.	true	true
ranger.unixauth.service.hostname	The address of the host where the UNIX authentication service is running.	{{ugsync_	l{(d ِstɡ̀) ync_host} }
ranger.unixauth.service.port	The port number on which the UNIX authentication service is running.	5151	5151

Table 4.10. UNIX Authentication Settings



Note

Properties with value $\{ \{xyz\} \}$ are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

Add Service Wizard

du Service wizaru			^
	 Ranger Settings 		
	External URL	http://c6403.ambari.apache.org/6080	c
	Authentication method	LDAP ACTIVE_DIRECTORY	
		â.	
	HTTP enabled	8 a c	
	 Unix Authentication Se 	ttings	
	Allow remote Login	true	a c
	ranger.unixauth.service. hostname	((ugsync_host())	a c
	ranger.unixauth.service. port	5151	# C
	 Knox SSO Settings 		
	Advanced ranger-admit	in-site	

4.3.2.5.2. Configuring Ranger LDAP Authentication

Use the following steps to configure Ranger authentication for LDAP.

- 1. Select the Advanced tab on the Customize Services page.
- 2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the External URL box in the format http://<your_ranger_host>:6080.

- 3. Under Ranger Settings, select LDAP.
- 4. Under LDAP Settings, set the following properties.

Table 4.11. LDAP Authentication Settings

Property	Description	Default Value	Example Value
ranger.ldap.base.dn	The Distinguished Name (DN) of the starting point for directory server searches.	dc=example,dc=com	dc=example,dc=com
Bind User	The full Distinguished Name (DN), including Common Name (CN) of an LDAP user account that has privileges to search for users. This is a macro variable value that is derived from the Bind User value from Ranger User Info > Common Configs .	{{ranger_ug_ldap_bind_d	r{}}anger_ug_ldap_bind_d
Bind User Password	Password for the Bind User. This is a macro variable value that is derived from the Bind User Password value from Ranger User Info > Common Configs.		
ranger.ldap.group. roleattribute	The LDAP group role attribute.	cn	cn
ranger.ldap.referral	See description below.	ignore	follow ignore throw
LDAP URL	The LDAP server URL. This is a macro variable value that is derived from the LDAP/AD URL value from Ranger	{{ranger_ug_ldap_url}}	{{ranger_ug_ldap_url}}

Property	Description	Default Value	Example Value
	User Info > Common Configs.		
ranger.ldap.user. dnpattern	The user DN pattern is expanded when a user is being logged in. For example, if the user "Idapadmin" attempted to log in, the LDAP Server would attempt to bind against the DN "uid=Idapadmir using the password the user provided>	uid={0},ou=users, dc=xasecure,dc=net ,ou=users,dc=example,dc=	cn=ldapadmin,ou=Users, dc=example,dc=com
User Search Filter	The search filter used for Bind Authentication This is a macro variable value that is derived from the User Search Filter value from Ranger User Info > User Configs.		e á{(dafitjer }∳g_ldap_user_searchfilt



Note

Properties with value $\{ \{xyz\} \}$ are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

There are three possible values for ranger.ldap.referral: follow, throw, and ignore. The recommended setting is follow.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to follow, the LDAP service provider processes all of the normal entries first, and then follows the continuation references.
- When this property is set to throw, all of the normal entries are returned in the enumeration first, before the ReferralException is thrown. By contrast, a

"referral" error response is processed immediately when this property is set to follow or throw.

• When this property is set to ignore, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search.

Add Service Wizard				х
	Ranger Settings			
	External URL	http://c6403.ambari.apache.org.6080	c	
	Authentication method	LDAP ACTIVE_DIRECTORY UNIX NONE		
	HTTP enabled	፼ ≗ C		
	LDAP Settings			
	ranger.ldap.base.dn	dc=example,dc=com	a c	
	Bind User	{{ranger_ug_ldap_bind_dn}}	a c	
	Bind User Password			
	ranger.ldap.group. roleattribute	cn	a c	
	ranger.ldap.referral	ignore	a c	
	LDAP URL	{{ranger_ug_ldap_urt}}	e c	
	ranger.ldap.user. dnpattern	uid=(0),ou-users,do-xasecure,do-net	e c	
	User Search Filter	{{ranger_ug_ldap_user_searchfilter}}	e c	
	 Knox SSO Settings 			
	Advanced ranger-adm	nin-ste		
	Advanced ranger-env	,		
	Advanced ranger-ugs	ync-ste		
	Custom admin-proper	rties		

4.3.2.5.3. Configuring Ranger Active Directory Authentication

Use the following steps to configure Ranger authentication for Active Directory.

- 1. Select the Advanced tab on the Customize Services page.
- 2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the External URL box in the format http://<your_ranger_host>:6080.
- 3. Under Ranger Settings, select ACTIVE_DIRECTORY.
- 4. Under AD Settings, set the following properties.

Table 4.12. AD Settings

Property	Description	Default Value	Example Value	
ranger.ldap.ad.base.dn	The Distinguished Name (DN) of the starting point for directory server searches.	dc=example,dc=com	dc=example,dc=com	
ranger.ldap.ad.bind.dn	The full Distinguished Name (DN), including Common Name (CN) of an LDAP user account that has privileges to search for users. This is a macro variable value that is derived from the Bind User value from Ranger User Info > Common Configs .	{{ranger_ug_ldap_bind_dn}	}{ {ranger_ug_ldap_bind_dn} }	}
ranger.ldap.ad.bind.passwor	Password for the bind.dn. This is a macro variable value that is derived from the Bind User Password value from Ranger User Info > Common Configs.			
Domain Name (Only for AD)	The domain name of the AD Authentication service.		dc=example,dc=com	
ranger.ldap.ad.referral	See description below.	ignore	follow ignore throw	
ranger.ldap.ad.url	The AD server URL. This is a macro variable value that is derived from the LDAP/ AD URL value from Ranger User Info > Common Configs.	{{ranger_ug_ldap_url}}	{{ranger_ug_ldap_url}}	
ranger.ldap.ad.user.searchfil	tehe search filter used for Bind Authentication. This is a macro variable value that is derived from the User Search Filter value from Ranger User Info > User Configs.	{{ranger_ug_ldap_user_sea	(†íɨᡶᠣg) =)_ug_ldap_user_searc	chfilter}



Note

Properties with value $\{ \{xyz\} \}$ are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

There are three possible values for ranger.ldap.ad.referral: follow, throw, and ignore. The recommended setting is follow.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

• When this property is set to follow, the AD service provider processes all of the normal entries first, and then follows the continuation references.

- When this property is set to throw, all of the normal entries are returned in the enumeration first, before the ReferralException is thrown. By contrast, a "referral" error response is processed immediately when this property is set to follow or throw.
- When this property is set to ignore, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search. In the case of AD, a PartialResultException is returned when referrals are encountered while search results are processed.

Add Service Wizard				х
	Ranger Settings			
	External URL	http://o6403.ambari.apache.org:6080) c	
	Authentication method	LDAP ACTIVE_DIRECTORY UNIX NONE		
	HTTP enabled	Ø ≜ C		
	 AD Settings 			
	ranger.ldap.ad.base.dn	dc=example, dc=com	a c	
	ranger.ldap.ad.bind.dn	{{ranger_ug_ldap_bind_dn}}	a c	
	ranger.ldap.ad.bind. password			
	Domain Name (Only for AD)	dc=hwqs,dc=hortonworks,dc=com) #	
	ranger.ldap.ad.referral	ignore	a c	
	ranger.ldap.ad.url	((ranger_ug_ldap_ur())	a c	
	ranger.klap.ad.user. searchfilter	{{ranger_ug_idap_user_searchfilter}}	e c	
	 Knox SSO Settings 			
	Advanced ranger-admi	n-site		

When you have finished configuring all of the Customize Services Settings, click **Next** at the bottom of the page to continue with the installation.

5. When you save the authentication method as Active Directory, a Dependent Configurations pop-up may appear recommending that you set the authentication method as LDAP. This recommended configuration should not be applied for AD, so you should clear (un-check) the **ranger.authentication.method** check box, then click **OK**.

Dependent Configura	ntions					Х
Based on your configuration changes, Ambari is recommending the following dependent configuration changes. Ambari will update all checked configuration changes to the Recommended Value. Uncheck any configuration to retain the Current Value.						
Property	Service	Config Group	File Name	Current Value	Recommended Value	
ranger.authentication.method	Ranger	Default	ranger-admin-site	UNIX	LDAP	
-						
					Cancel	ОК

4.3.3. Complete the Ranger Installation

1. On the Review page, carefully review all of your settings and configurations. If everything looks good, click **Deploy** to install Ranger on the Ambari server.

Add Service Wizard	
ADD SERVICE WIZARD Choose Services Assign Masters	Please review the configuration before installation
Assign Slaves and Clients	
Customize Services	Admin Name : admin
Configure Identities	Cluster Name : HDF
Review	Total Hosts : 3 (0 new)
install, Start and Test	Repositories:
Summary	debian7 (HDF-2.0): http://s3.amazonaws.com/dev.hortonworks.com/HDF/debian7/2.x/BUILDS/2.0.0.0-567
	debian7 @HDP-UTILS-1.1.0.21): http://public-repo-1.hortorworks.com/HDP-UTILS-1.1.0.21/repos/debian6
	redhat6 (HDF-2.0): http://s3.amazonawa.com/dev.hortonworks.com/HDF/centos6/2.x/BUILDS/2.0.0.0-567
	redhat6 (HDP-UTILS-1.1.0.21): http://public-repo-1.hortorworks.com/HDP-UTILS-1.1.0.21/repos/centos6
	redhat7 (HDF-2.0): http://s3.amazonaws.com/dev.hortonworks.com/HDF/centos7/2.x/BUILDS/2.0.0.0-567 redhat7 (HDP-UTILS-1.1.0.21): http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.21/repos/centos7 suse11 (HDF-2.0): http://s3.amazonaws.com/dev.hortonworks.com/HDF/suse11sp3/2.x/BUILDS/2.0.0.0-567
	Back Print Deploy

2. When you click **Deploy**, Ranger is installed on the specified host on your Ambari server. A progress bar displays the installation progress.

ADD SERVICE WIZARD Choose Services	Install, Start and	Test			
Assign Masters	Please wait while the selected service	ces are installed and sta	rted.		
Assign Slaves and Clients Customize Services					24 % overall
Configure Identities		5	how: N (2)	In Progress (3) Warning (3) 5	kuccess.db Eal.db
Review	Host	Status		Message	
Install, Start and Test	c6401.ambari.apache.org		8%	Installing Ranger Admin	
Summary	o6402.ambari.apache.org		33%	Install complete (Walting t	o start)
	o6403.ambari.apache.org		33%	Install complete (Waiting t	o start)
	3 of 3 hosts showing - Show All		1	Rox 25 0 1-3 of 3	× + + +

3. When the installation is complete, a Summary page displays the installation details. You may need to restart services for cluster components after installing Ranger.



Note

If the installation fails, you should complete the installation process, then reconfigure and reinstall Ranger.

4.3.4. Advanced Usersync Settings

To access Usersync settings, select the **Advanced** tab on the Customize Service page. Usersync pulls in users from UNIX, LDAP, or AD and populates Ranger's local user tables with these users.

4.3.4.1. UNIX Usersync Settings

If you are using UNIX authentication, the default values for the Advanced ranger-ugsyncsite properties are the settings for UNIX authentication.

 Advanced ranger-ugsy 	nc-site			
ranger.usersync.idap. bindkeystore		â	0	
ranger.usersync.ldap. Idapbindpassword	Type password			
ranger.usersync.group. memberattributename		8	•	c
ranger.usersync.group. nameattribute		8	•	c
ranger.usersync.group. objectclass		8	•	c
ranger.usersync.group. searchbase		8	•	c
ranger.usersync.group. searchenabled	false	8	•	c
ranger.usersync.group. searchfilter		8	•	c
ranger.usersync.group. searchscope		8	•	c
ranger.usersync.group. usermapsyncenabled	false	8	•	c
ranger.usersync.idap. searchBase	dc=hadoop,dc=apache,dc=org	8	•	c
ranger.usersync.source. impl.class	org.apache.ranger.unixusersync.process.UnixUserGroupBuilder	8	0	c
ranger.usersync. credstore.filename	/usr/hdp/current/ranger-usersync/conf/ugsync.jceks	<u>a</u>	•	c
ranger.usersync.enabled	true		•	c
ranger.usersync. filesource.file	/tmp/usergroup.txt	8	•	c
ranger.usersync. filesource.text.delimiter		8	•	c
ranger.usersync. keystore.file	/usr/hdp/current/ranger-usersync/cont/unixauthservice.jks	8	0	c

4.3.4.2. Required LDAP and AD Usersync Settings

If you are using LDAP authentication, you must update the following Advanced rangerugsync-site properties.

Table 4.13. LDAP Advanced ranger-ugsync-site Settings

Property Name	LDAP Value
ranger.usersync.ldap.bindkeystore	Set this to the same value as the ranger.usersync.credstore.filename property, i.e, the default value is /usr/hdf/current/ranger- usersync/conf/ugsync.jceks
ranger.usersync.ldap.bindalias	ranger.usersync.ldap.bindalias

Property Name	LDAP Value
ranger.usersync.source.impl.class	ldap

Table 4.14. AD Advanced ranger-ugsync-site Settings

Property Name	LDAP Value
ranger.usersync.source.impl.class	ldap

4.3.4.3. Additional LDAP and AD Usersync Settings

If you are using LDAP or Active Directory authentication, you may need to update the following properties, depending upon your specific deployment characteristics.

Table 4.15. Advanced ranger-ugsync-site Settings for LDAP and AD

Property Name	LDAP ranger-ugsync-site Value	AD ranger-ugsync-site Value
ranger.usersync.ldap.url	ldap://127.0.0.1:389	ldap://ad-conrowoller- hostname:389
ranger.usersync.ldap.binddn	cn=ldapadmin,ou=users, dc=example,dc=com	cn=adadmin,cn=Users, dc=example,dc=com
ranger.usersync.ldap.ldapbindpassword	secret	secret
ranger.usersync.ldap.searchBase	dc=example,dc=com	dc=example,dc=com
ranger.usersync.source.impl.class	org.apache.ranger. ladpusersync. process.LdapUserGroupBu	ilder
ranger.usersync.ldap.user.searchbase	ou=users, dc=example, dc=com	dc=example,dc=com
ranger.usersync.ldap.user.searchscope	sub	sub
ranger.usersync.ldap.user.objectclass	person	person
ranger.usersync.ldap.user.searchfilter	Set to single empty space if no value. Do not leave it as "empty"	(objectcategory=person)
ranger.usersync.ldap.user.nameattribute	uid or cn	sAMAccountName
ranger.usersync.ldap.user.groupnameattribute	memberof, is member of	member of, is member of
ranger.usersync.ldap.username.caseconversion	none	none
ranger.usersync.ldap.groupname.caseconversion	none	none
ranger.usersync.group.searchenabled *	false	false
ranger.usersync.group.usermapsyncenabled *	false	false
ranger.usersync.group.searchbase *	ou=groups, dc=example, dc=com	dc=example,dc=com
ranger.usersync.group.searchscope *	sub	sub
ranger.usersync.group.objectclass *	groupofnames	groupofnames

Property Name	LDAP ranger-ugsync-site Value	AD ranger-ugsync-site Value
ranger.usersync.group.searchfilter *	needed for AD authentication	(member=CN={0}, OU=MyUsers, DC=AD- HDF, DC=COM)
ranger.usersync.group.nameattribute *	cn	cn
ranger.usersync.group.memberattributename *	member	member
ranger.usersync.pagedresultsenabled *	true	true
ranger.usersync.pagedresultssize *	500	500
ranger.usersync.user.searchenabled *	false	false
ranger.usersync.group.search.first.enabled *	false	false

* Only applies when you want to filter out groups.

After you have finished specifying all of the settings on the Customize Services page, click **Next** at the bottom of the page to continue with the installation.

4.3.5. Configuring Ranger for LDAP SSL

You can use the following steps to configure LDAP SSL using self-signed certs in the default Ranger User Sync TrustStore.

- The default location is /usr/hdf/current/ranger-usersync/conf/ mytruststore.jks for the ranger.usersync.truststore.file property.
- 2. Alternatively, copy and edit the self-signed ca certs.
- 3. Set the ranger.usersync.truststore.file property to that new cacert file.

```
cd /usr/hdp/<version>/ranger-usersync
service ranger-usersync stop
service ranger-usersync start
```

Where cert.pem has the LDAPS cert.

4.3.6. Setting up Database Users Without Sharing DBA Credentials

If do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the dba_script.py Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. You can then run the normal Ambari Ranger installation without specify a DBA user name and password.

To create Ranger DB users using the dba_script.py script:

1. Download the Ranger rpm using the yum install command.

```
yum install ranger-admin
```

- 2. You should see one file named dba_script.py in the /usr/hdf/current/ ranger-admin directory.
- 3. Get the script reviewed internally and verify that your DBA is authorized to run the script.
- 4. Execute the script by running the following command:

python dba_script.py

- 5. Pass all values required in the argument. These should include db flavor, JDBC jar, db host, db name, db user, and other parameters.
 - If you would prefer not to pass runtime arguments via the command prompt, you can update the /usr/hdf/current/ranger-admin/install.properties file and then run:
 - python dba_script.py -q

When you specify the -q option, the script will read all required information from the install.properties file

• You can use the -d option to run the script in "dry" mode. Running the script in dry mode causes the script to generate a database script.

python dba_script.py -d /tmp/generated-script.sql

Anyone can run the script, but it is recommended that the system DBA run the script in dry mode. In either case, the system DBA should review the generated script, but should only make minor adjustments to the script, for example, change the location of a particular database file. No major changes should be made that substantially alter the script – otherwise the Ranger install may fail.


The system DBA must then run the generated script.

6. Run the Ranger Ambari install procedure, but set **Setup Database and Database User** to **No** in the Ranger Admin section of the Customize Services page.

4.3.7. Updating Ranger Admin Passwords

For the following users, if you update the passwords on the Ranger Configs page, you must also update the passwords on the Configs page of each Ambari component that has the Ranger plugin enabled. Individual Ambari component configurations are not automatically updated – the service restart will fail if you do not update these passwords on each component.

- Ranger Admin user The credentials for this user are set in Configs > Advanced rangerenv in the fields labeled admin_username (default value: admin) and admin_password (default value: admin).
- Admin user used by Ambari to create repo/policies The user name for this user is set in Configs > Admin Settings in the field labeled Ranger Admin username for Ambari (default value: amb_ranger_admin). The password for this user is set in the field labeled Ranger Admin user's password for Ambari. This password is specified during the Ranger installation.



The following image shows the location of these settings on the Ranger Configs page:

4.3.8. Enabling Ranger Plugins

If you did not enable Ranger plugins during the initial Ranger installation, you can enable them later. This section describes how to enable each of these plugins. For performance reasons, it is recommended that you store audits in Solr, and not in a database.

If you are using a Kerberos-enabled cluster, there are a number of additional steps you must follow to ensure that you can use the Ranger plugins on a Kerberos cluster.


The following Ranger plugins are available:

- Kafka [56]
- Storm [60]
- NiFi [63]

4.3.8.1. Kafka

Use the following steps to enable the Ranger Kafka plugin.

1. On the Ranger Configs page, select the **Ranger Plugin** tab.



2. Under Kafka Ranger Plugin, select **On**, then click **Save** in the black menu bar.

Ranger Plugin		
HDFS Ranger Plugin	Hbase Ranger Plugin	Knox Ranger Plugin
	_	
YARN Ranger Plugin	Storm Ranger Plugin	Kafka Ranger Plugin
ON	OFF	ON
Hive Ranger Plugin		
ON		


3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.

Sav	e Configuration	Х
Notes	Enabled Ranger for Kafka	
	Cancel Discard Sa	ave

4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.

De	ependent Configura	ations				X
	ased on your configuration change mbari will update all checked conf					
	Property	Service	Config Group	File Name	Current Value	Recommended Value
•	authorizer.class.name	Kafka	Default	kafka-broker		org.apache.ranger.authorization.kafk a.authorizer.RangerKafkaAuthorizer
0	content	Kafka	Default	kafka-log4j	# # # Licensed to the Apache Softw are Foundation (ASF) under one # or more contributor license agreement s. See the NOTICE file # distributed with this work for additional informat ion # regarding copyright ownership. The ASF licenses this file # to you un der the Apache License, Version 2.0 (the # "License"); you may not use t his file except in compliance # with t he License. You may obtain a copy of the License at # # http://www.apa che.org/licenses/LICENSE-2.0 # # U niess required by applicable law or a greed to in writing, # software distrib uted under the License is distributed on an # "AS IS" BASIS, WITH-OUT W ARRANTES OR CONDITIONS OF A NY # KIND, either express or implie d. See the License for the # specific language governing permissions and limitatione. # # # Interse. # # #	# # # Licensed to the Apache Softw are Foundation (ASP) under one # or more contributor license agreement s. See the NOTICE file # distributed with this work for additional informat ion # regarding copyright ownership. The ASP licenses this file # to you un der the Apache License, Version 2.0 (the # "License"); you may not use t his file except in compliance # with t he License. You may obtain a copy of the License at # # http://www.apa che.org/licenses/LICENSE-2.0 # U niess required by applicable law or a greed to in writing, # software distrib- uted under the License is distributed on an # "AS IS" BASIS, WITHOUT W ARRANTIES OR CONDITIONS OF A NY # KIND, either express or implie d. See the License for the # specific language governing permissions and Imitations # under the License at # # #
						Cancel OK


5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Kafka** in the navigation menu, then select **Restart > Restart All Affected** to restart the Kafka service and load the new configuration.

🛛 🝌 Ambari test_o	cluster (Dops) Balanta		Dashboard Se	rvices Hosts 1	Alerts Ad	min	🗰 🔺 admin 🔹
O HDFS	Summary Configs						Service Actions -
MapReduce2 YARN	C Restart Required: 1 O	omponent on 1 Host					Restart -
□ Tez © Hive 🚦	Group Default (1) -	Manage Config Groups			Filter	Res	tart All Affected
HBase			V1 admin				
Sqoop Oozle	4 minutes ago HC	8 hours ago HDP-2.3	16 days-ago HDP-2.3				
O ZooKeeper	🗶 🕶 🔽 admin as	thored on Wed, Dec 09, 2015 1	19:31				Discard Save
Falcon Storm	 Kafka Broker 						
Flume Accumulo	Kafka Broker host	o6403.ambari.apache.org					
 Ambari Metrics Atlas 	zookeeper.connect	o6403.ambari.apache.org:218 /kafka-logs	81			≙ 0	c
 Kafka C Knox 						⊜ 0	a
Mahout	log.retention.hours	168				≞ 0	c
Ranger Slider	log.roll.hours	168 PLAINTEXT://localhost:6667				a 0	
 SmartSense Spark 	101011010	- same an				- •	-
Actions -	 Advanced kafka-broke 	r					
	Advanced kafka-env						
	Advanced kafka-log4j						

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Kafka restart.



8. After Kafka restarts, the Ranger plugin for Kafka will be enabled.

4.3.8.2. Storm

Use the following steps to enable the Ranger Storm plugin.

1. On the Ranger Configs page, select the Ranger Plugin tab.

 Indres VARN Mapfleduce2 Tez Hitase Pig Stoop C Cozie Cozie Ranger Admin Ranger Dugin Farger Audit Ranger Plugin For 23 Ranger Plugin For 8 Attas Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin Kons Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin Kons Ranger Plugin Kasha Ranger Plugin <l< th=""><th></th><th>🝌 Ambari</th><th>Sandbox</th><th>Cape Balarta</th><th>Dashboard Services Hos</th><th>ts Alerts Admin</th><th>💷 🔺 admin 🕶</th></l<>		🝌 Ambari	Sandbox	Cape Balarta	Dashboard Services Hos	ts Alerts Admin	💷 🔺 admin 🕶
MapHeducad Inter Hue Hue Hue Hue Hue Hue Hue Hue Hue Sopop Coolespeer Fanne Antheni Metrices Kinsk Kinsk Kinsk VMW Ranger Plugin Hue	0	HDFS		Summary Configs	Quick Links-		Service Actions •
Inter Inter </td <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td>							
Hve C Hilbane Pig Sqoop Coxie Zookkepper Coxie Zookkepper Falcon Coxie Falcon Coxie Falcon Coxie Falcon Coxie Falcon Coxie Falcon Coxie Falcon Coxie Falcon Coxie Falcon Coxie Horis Ranger Plugin Hose Ranger Plugin Katala Vulti Ranger Plugin Hose Ranger Plugin Katala Vulti Ranger Plugin Horis Ranger Plugin Katala Vulti Ranger Plugin Katala Vulti Ranger Plugin Katala Vulti Ranger Plugin Katala Spark Log Sterr Coxie </td <td>•</td> <td>MapReduce2</td> <td></td> <td>Group Default (1) Manage Config Group</td> <td>ps</td> <td>Filter</td> <td>= -</td>	•	MapReduce2		Group Default (1) Manage Config Group	ps	Filter	= -
 Hva C 		Tez					
Image x1. No. with authored on FrL, Juli 22, 2016 19:25 Discard Bit Sqoop C Oorie Ranger Admin Ranger Plugin Ranger Audit Ranger Tagsyno Advanced Palcon C Ranger Plugin Hose Ranger Plugin Kriss Ranger Plugin Kriss Ranger Plugin Port POPS Ranger Plugin Hose Ranger Plugin Kriss Ranger Plugin Kriss Ranger Plugin Arbbarl Metrics ON ON ON ON ON Arbbarl Metrics ON ON ON ON ON Kafsta VMIN Ranger Plugin Boom Ranger Plugin Kots Ranger Plugin ON ON Kafsta VMIN Ranger Plugin ON	۰	Hive	0	a moment ago 11 days ago	11 days ago		
Stoop C Stoop C Cotie Ranger Claer info Ranger Admin Ranger Plugin Stoom C Falcon C Falcon C Falme HOFS Ranger Plugin HOFS Ranger Plugin Hoase Ranger Plugin Krinka C Atlas C Kafka VAIN Ranger Plugin Kafka VAIN Ranger Plugin Kafka VAIN Ranger Plugin Kafka VAIN Ranger Plugin Kafka C Kafka VAIN Ranger Plugin Kafka VAIN Ranger Plugin Kafka VAIN Ranger Plugin Kafka C Kafka C <	۰	HBase			P-2.5 HDP-2.5		
 Oazie Ranger Admin Ranger User Info Ranger Plugin Ranger Tigsync Advanced Hors Ranger Plugin Ori <pori< p=""> Ori <pori< p=""> Ori Ori Ori <</pori<></pori<>		Pig	1	x • V3 v admin authored on Fri, Jul 22, 2	016 19:25		Discard Save
Zookkeper		Sqoop	0				
• Falcon • C • Storm • C • Flume HOPS Ranger Plugin Knox Ranger Plugin • Ambari Metrics • C • Ambari Metrics • C • Atabas • C • Kafka • VANN Ranger Plugin • Log Bearch • Orit • Spark Hvin Ranger Plugin	۰	Oozie		Ranger Admin Ranger User Info Ranger Plugin	Ranger Audit Ranger Tagsync Advanced	1	
Born C Born C Plume HOFS Ranger Plugin Ambari Metrics CN Atlas C Atlas C Kinox CN Kinox CN Bernh Example Plugin Kafka VANN Ranger Plugin Kafka VANN Ranger Plugin Kafka VANN Ranger Plugin Bernh CM Bernh CM Spark Hwe Ranger Plugin Aflas Flarger Plugin Aflas Ranger Plugin CM CM	۰	ZooKeeper					
Borm C Flame HDFS Ranger Plugin Arbani Metrics CM Atlas CM Katka VAINN Ranger Plugin Katka VAINN Ranger Plugin Katka VAINN Ranger Plugin Biorm Ranger Plugin Katka Ranger Plugin Katka VAINN Ranger Plugin Biorm Ranger Plugin Katka Ranger Plugin Katka VAINN Ranger Plugin Biorm Ranger Plugin GN Biorm Ranger Plugin GN Biorm Ranger Plugin GN Col Col	۰	Falcon	ø	Banger Plugin			
Anbari Metrics GN GN GN Ablas C Kalka VAIN Ranger Plugin Blorm Ranger Plugin Kaha Ranger Plugin Kinox GN Cm GN Log Bearch GN Cm GN Panger Hve Ranger Plugin Atlas Ranger Plugin GN Spark Hve Ranger Plugin Atlas Ranger Plugin GN Zeopelin Notrebook GN Cm Cm			ø	0			
Atlas C Kafka VANN Renger Plugin Knox CM Log Search CM Panger Panger Ven Panger Plugin Adas Ranger Plugin Kos CM CM CM							
Kaka YAIN Ranger Plugin Bitom Ranger Plugin Kinka Ranger Plugin Log Bearch CM Cm CM Panger Hve Ranger Plugin Atlas Ranger Plugin CM Zeppelin Nothbook CM Cm Cm	0			ON	ON	ON	
Knox Eiom Ranger Plugin Eiom Ranger Plugin Kuha Ranger Plugin Log Search Imager Plugin Imager Plugin Imager Plugin Parger Plunger Plugin Atlas Ranger Plugin Imager Plugin Spark Hve Ranger Plugin Atlas Ranger Plugin Imager Plugin Zeppelin Notebook Imager Plugin Imager Plugin Imager Plugin			0				
Log Search GN GN GN Planger Spark Hve Rager Plugin Aflas Rager Plugin Zeppelin Notebook GN GN				YARN Ranger Plugin	Storm Ranger Plugin	Kafka Ranger Plugin	
Log Search Parger S Spark Hwe Ranger Plugin Zeppelin Col Notebook				ON	Corp.	ON	
Spark Hve Ranger Plugin Aflas Ranger Plugin Zeppelin Ost Silder	-		-	_		_	
Cappelin Cat Notwbook				kilon Bannar Dunin	Atlas Bannar Busin		
Notebook							
	Ŭ			ON I	6.17		
		Slider					
		Actions a					
Actions *		Actions *					

2. Under Storm Ranger Plugin, select **On**, then click **Save** in the black menu bar.

Ranger Plugin		
HDFS Ranger Plugin	Hbase Ranger Plugin	Knox Ranger Plugin
YARN Ranger Plugin	Storm Banger Plugin	Kafka Ranger Plugin
Hive Ranger Plugin		

3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.

Sav	e Configuration		х
Notes	Enabled Ranger for Storm		
1		Cancel Discard	Save

4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.

C	Dependent Configurations									
	Based on your configuration changes, Ambari is recommending the following dependent configuration changes. Ambari will update all checked configuration changes to the Recommended Value. Uncheck any configuration to retain the Current Value.									
	9 Property	Service	Config Group	File Name	Current Value	Recommended Value				
	ranger-storm-plugin-enabled	Storm	Default	ranger-storm-plugin-proper ties	No	Yes				
						Cancel	ок			


5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Storm** in the navigation menu, then select **Restart > Restart All Affected** to restart the Storm service and load the new configuration.

🔬 Ambari 🛛 test1 💼	opa <mark>7 slorta</mark>		D	ashb	oard	Services	Hosts 1	Alerts	Admin	💷 🔺 admin 🗝
HDFS MapReduce2	Summary Configs		٩	ulck I	Links	•				Service Actions *
O YARN	C Restart Required: 4 Co	omponents on 1 Host								Restart -
□ Tez O Hive C	Group Storm Default (1)	Manage Config G	roups					Fib	er	tart All Anected
A HBase		admin 🔽 ad				admin 🔽	admin	VI	admin	
🖵 Sqoop	a moment ago HD	about a minute ago P-2.3 HDP-		minut		P-2.3	0 days ago HDP-2.3	110	HDP-2.3	
© ZooKeeper	🗶 🔹 V5 🖌 admin au	rthored on Fri, Sep 11, 20	15 13:55							Discard Save
 Falcon Storm @ 	 Nimbus 									
Flume Accumulo	nimbus.reassign	0 ÷ • °								
Ambari Metrics Atlas	nimbus.childopts	-Xmx1024m _JAAS_PL nimbus/contrib/storm-ji 1.0.4.jar=host=localhos p/current/storm-nimbus	t,port=8649	imxet 9,wire	rio- form	at31x=true,mo	de-multicast,o	onfig=/usr	nhd ^a C	,
Kafka Knox Mahout	nimbus.cleanup.inbox. freq.secs	600 E	seconds	8	•	c				
Ranger Silder	nimbus.file.copy. expiration.secs	600	seconds	-	•	c				
 Spark 	nimbus.inbox.jar. expiration.secs	3600	seconds	-	0	c				
Actions *	nimbus.monitor.freq.secs	10	seconds	-	0	e				
	nimbus.supervisor. timeout.secs	60	seconds	<u>a</u>	0	c				
	nimbus.task.launch.secs	120	seconds	-	0	e				
	nimbus.task.timeout. secs	30	seconds	₽	۰	c				
	nimbus thrift	1048576	hytes 4			•				

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Storm restart.



8. After Storm restarts, the Ranger plugin for Storm will be enabled.


4.3.8.3. NiFi

Use the following steps to enable the Ranger NiFi plugin.

- 1. On the Ranger Configs page, select the Ranger Plugin tab.
- 2. Under NiFi Ranger Plugin, select **ON**, then click **Save** in the black menu bar.

🔬 Ambari 🛛 HDF 🜆	l ops 8 akerts	Dashboard Services	Hosts Alerts Admin	🔠 🔺 admin •
ZooKeeper	Summary Configs	Quick Links -		Service Actions *
 Storm Ambari Infra 	Group Default (3) Manage Config G	roups	Filter	•
Ambari Metrics Kafka Log Search	C C C C C C C C C C C C C C C C C C C	admin ago HDP-2.0 HDP-2.0		
Ranger	🗶 🔹 🔽 admin authored on Thu, Sep	08, 2016 18:54		Discard Save
Kerberos NIFI Actions -	Ranger Admin Ranger User Info Ranger Pit	igin Ranger Audit Ranger Tagsyno Advan	ced	
Action is *	Ranger Plugin NIFI Ranger Plugin	Storm Ranger Plugin	Kafka Ranger Plugin ON	


- 3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.
- 4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.
- 5. Click **OK** on the **Save Configuration Changes** pop-up.



6. From the left navigation menu click **Actions**, then **Restart All Required** to restart NiFi and any additional plugins you have enabled.

🔜 🚕 Ambari HE	F Cores Daterts		Dashboard	Services	Hosts	Alerts	Admin	ш	🛦 admin 🕶
O ZooKeeper	Summary Configs		Quick Links +						Service Actions •
Storm Ambari Infra	C Restart Required: 4 Oc	emponents on 3 Hosts						1	Restart +
Ambari Metrics Kafka	Summary								No alerts
 Log Search Ranger 	NE	 Started No skerts Started No skerts 							
Actions •		Started No electe I/I NIFi Certificate Authority	Live						
+ Add Service	Metrics						Actio	ms •	Last 1 hour •
Start Al Stop Al C Restart Al Rec	FlowFiles Received Last 5 mins 1	MBs Received Last 5 mins	FlowFiles Sent Las mins	15	MBs Sent Li	ist 5 mins	Flo	wfiles (Queued

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the NiFi restart along with any other servies requiring a restart.



8. After your services restart, the Ranger plugin is enabled.

4.4. Adding Users to Ranger

After installing Ranger and enabling the Ranger plugins, add users to Ranger.

1. From the Ranger UI, click **Settings**, then **Users/Groups**.

ge						4
	reage					
lsen						
List	t					
54	which for your users			0	Add New	User Set Visibility *
		Email Address	Role	User Source	Groups	Visibility
	admin		(C. 11)	Internal		1000
	rangerusersync		(ALCONG)	Internal	-	whether
	rangertagsync		Address	Internal	-	whether
	legsearch		Liner	External	(hadrop)	whether
	storm		Liner	External	Bardweg .	whether
	infra-solr		Lines	Enternal	(hadrog)	WARKE
	zookeeper		Liner	External	(hadrog)	whether
	arts		Maar	Enternal	(hading)	and the second sec
	ambari qa		Liner	External	users hadrop	which has
	kafka		Liner	External	(hadrop)	whether .
	ranger		User	External	rarger hadoop	and the second sec
	nit		User	External	Cold Randomy	The local division of
	centos		Liner	External	wheel adm center	10000
	amb_ranger_admin		(Address)	Internal	-	whether
	abajwa-hdf-ge-docs-1.openstack/ocal@HORTONWORKS		User	Internal	LIBETS	Walkie
	abajwa-hdf-ge-docs-2.openstacklocal@HORTONWORKS		User	Internal	LINETS .	whether
	abajwa hdf qe-docs-3.openstack/ocal@HORTONWORKS		User	Internal	Silver's	Walkie
	storm-hdf		User	External	-	whether
	stormtestuser		User	External	-	Visible
	rangerlookup		User	External	-	Visite I

2. Click Add New User.

- 3. In the User Detail screen, provide:
 - User Name in the CN=<host> OU=<realm> format. If you have set up identity mapping, use the <host>@<realm> format.
 - The password the user will use to access Ranger.
 - The Role you want the user to have.
 - The Group you want the user to be part of.

Ranger OAccess N	lanager	🗅 Audit	Settings	
Users/Groups Vser Crea	ate			
User Detail				
User Name *				
New Password *				
Password Confirm *				
First Name *				
Last Name				
Email Address				
Select Role *			\$	
Group	Please selec	ct.	•	Ð
	Save	Cancel		

5. Authorization with Ranger

5.1. Creating Policies for NiFi Access

Once you have set up Ranger to manage NiFi authorization, you must create policies so that users can access and operate on the NiFi canvas.

- Creating Policies to View NiFi [67]
- Allowing Users Read and Write Access [69]

5.1.1. Creating Policies to View NiFi

To allow users to view the NiFi UI, create the following policies for each host:

- /flow read
- /proxy read/write

To create policies:

1. From the Ranger console, click the NiFi Ranger plugin.

	+
HDF_nifi	

- 2. From the List of Policies page, click Add New Policy.
- 3. In the Policy Details dialog, create the /flow and /proxy policies.

olicy Details :					
Policy Type	Access				
Policy Name *	en	ibled 🔘			
iFi Resource Identifier *	(Inc	dude 🔘			
Audit Logging					
1.0001 0.000-0	YES 💮				
Description					
Description					
Description					
Description	Select Group	Select User	Permissions	Delegate Admin	
Description		Select User Belect User	Permissions Add Permissions	Delegate Admin	
	Select Group			-	

- 4. To create the /flow policy:
 - a. Provide the following information:
 - Policy Name /flow
 - NiFi Resource Identifier-/flow
 - Select Users and Groups you want to immediately add.
 - Add Read permission
 - b. Click Add.
- 5. To create the /proxy policy:
 - a. Provide the following information:
 - Policy Name /proxy
 - NiFi Resource Identifier-/proxy
 - Select Users and Groups you want to immediately add.
 - Add **Read** and **Write** permissions.
 - b. Click Add.

5.1.2. Allowing Users Read and Write Access

To allow users complete read and write access to NiFi:

- 1. From the **Policy Details** page, select the global NiFi policy.
 - Policy Name all nifi-resource
 - NiFi Resource Identifier x
- 2. Add users.
- 3. Add Read and Write permissions.

5.2. Create a Kafka Policy

To add a new policy to an existing Kafka service:

1. On the Service Manager page, select an existing service under Kafka.

► KAFKA +
C6401 TEST kafka
C6401 TEST kafka
C6401 TEST kafka
C6401 TEST kafka

The List of Policies page appears.

anger	🛡 Access Manager 🗈	Audit 🔶 🤅	Settings				🔒 admi
Service Manag	er 🔪 Example-Service Polici	es					
ist of Policie	s : Example-Service						
Q. Search f	or your policy				0		Add New Policy
Policy ID	Policy Nam	e	Status	Audit Logging	Groups	Users	Action

2. Click Add New Policy.

The Create Policy page appears.

Ranger DAG	cess Manager 🗈 Audi	t O Settings					🍰 admin
Service Manager	test Policies Create Polic	y					
Create Policy							
Policy Details :							
Polic	Type Access						
Policy N	ame *	E enab	led 🔘				
,	opic *	Inclu	ide 🔵				
	_						
Audit Li	oesine YES						
Desc	iption						
Allow Condition		6					
Allow Condition	5:						hide +
	Sele	ect Group	Select User	Policy Conditions	Permissions	Delegate Admin	
	Select Group	Sel	ect User	Add Conditions +	Add Permissions +	o 💌	
	+						
	Add Cancel						

3. Complete the Create Policy page as follows:

Table 5.1. Policy Details

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Торіс	A topic is a category or feed name to which messages are published.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 5.2. Allow Conditions

Label	Description
Select Group	 Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies). The public group contains all users, so granting access to the public group grants access to all users.
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range.
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.

Label	Description
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

- 4. You can use the Plus (+) symbol to add additional conditions. Conditions are evaluated in the order listed in the policy. The condition at the top of the list is applied first, then the second, then the third, and so on.
- 5. Click Add.

5.3. Create a Storm Policy

To add a new policy to an existing Storm service:

1. On the Service Manager page, select an existing service under Storm.

	+
<u>test-storm</u>	

The List of Policies page appears.

anger	O Access Manager	🗅 Audit 🛛 🗢	Settings				🔒 admi
Service Manag	er 🔪 Example-Service Pol	icies					
st of Policie	s : Example-Service						
Q. Search fo	or your policy				0		Add New Policy
Policy ID	Policy Na	me	Status	Audit Logging	Groups	Users	Action

2. Click Add New Policy.

The Create Policy page appears.

Ranger	© Access Man	ager 🗅 A	Audit	• Settings				🍰 admin
Service Manag	ger 🔪 Storm_ser	vice1 Policies	Creat	e Policy				
Create Policy	y							
Policy Det	ails :							
	Policy Type	Access						
	Policy Name *				enabled			
Stor	m Topology *				Include			
	Description							
	Audit Logging	15		6				
Allow Con	ditions :							show +
							Delegate	
			Select Gr	oup	Select User	Permissions	Admin	
		Select G	roup		Select User	Add Permissions +	•	
		+						
		_	_					
		Add Cano	el					

3. Complete the Create Policy page as follows:

Table 5.3. Policy Details

Label	Description
Policy Name	Enter an appropriate policy name. This name is cannot be duplicated across the system. This field is mandatory.
Storm Topology	Enter an appropriate Topology Name.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 5.4. Allow Conditions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies). The public group contains all users, so granting access to the public group grants access to all users.
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated

Label	Description
	admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Since Storm does not provide a command line methodology for assigning privileges or roles to users, the User and Group Permissions portion of the Storm Create Policy form is especially important.

Table 5.5. Storm User and Group Permissions

Actions	Description
File upload	Allows a user to upload files.
Get Nimbus Conf	Allows a user to access Nimbus configurations.
Get Cluster Info	Allows a user to get cluster information.
File Download	Allows a user to download files.
Kill Topology	Allows a user to kill the topology.
Rebalance	Allows a user to rebalance topologies.
Activate	Allows a user to activate a topology.
Deactivate	Allows a user to deactivate a topology.
Get Topology Conf	Allows a user to access a topology configuration.
Get Topology	Allows a user to access a topology.
Get User Topology	Allows a user to access a user topology.
Get Topology Info	Allows a user to access topology information.
Upload New Credential	Allows a user to upload a new credential.
Admin	Provides a user with delegated admin access.

- 4. You can use the Plus (+) symbol to add additional conditions. Conditions are evaluated in the order listed in the policy. The condition at the top of the list is applied first, then the second, then the third, and so on.
- 5. Click Add.

6. NiFi Authorization

After you have configured NiFi to run securely and with an authentication mechanism, you must configure who has access to the system, and the level of their access. You can do this using *multi-tenant authorization*. Multi-tenant authorization enables multiple groups of users (tenants) to command, control, and observe different parts of the dataflow, with varying levels of authorization. When an authenticated user attempts to view or modify a NiFi resource, the system checks whether the user has privileges to perform that action. These privileges are defined by policies that you can apply system-wide or to individual components.

6.1. Authorizer Configuration

An *authorizer* grants users the privileges to manage users and policies by creating preliminary authorizations at startup.

Authorizers are configured using two properties in the *nifi.properties* file:

- The nifi.authorizer.configuration.file property specifies the configuration file where authorizers are defined. By default, the *authorizers.xml* file located in the root installation conf directory is selected.
- The nifi.security.user.authorizer property indicates which of the configured authorizers in the *authorizers.xml* file to use.

6.2. Authorizers.xml Setup

The *authorizers.xml* file is used to define and configure available authorizers. The default authorizer is the FileAuthorizer, however, you can develop additional authorizers as extensions. The FileAuthorizer has the following properties:

- Authorizations File The file where the FileAuthorizer stores policies. By default, the *authorizations.xml* in the *conf* directory is chosen.
- Users File The file where the FileAuthorizer stores users and groups. By default, the *users.xml* in the *conf* directory is chosen.
- Initial Admin Identity The identity of an initial admin user that is granted access to the UI and given the ability to create additional users, groups, and policies. This property is only used when there are no other users, groups, and policies defined.
- Legacy Authorized Users File The full path to an existing authorized-users.xml that is automatically converted to the multi-tenant authorization model. This property is only used when there are no other users, groups, and policies defined.
- Node Identity The identity of a NiFi cluster node. When clustered, a property for each node should be defined, so that every node knows about every other node. If not clustered, these properties can be ignored.

6.2.1. Initial Admin Identity (New NiFi Instance)

If you are setting up a secured NiFi instance for the first time, you must manually designate an "Initial Admin Identity" in the *authorizers.xml* file. This initial admin user is granted access to the UI and given the ability to create additional users, groups, and policies. The value of this property could be a DN (when using certificates or LDAP) or a Kerberos principal. If you are the NiFi administrator, add yourself as the "Initial Admin Identity".

Here is an example LDAP entry using the name John Smith:

Here is an example Kerberos entry using the name John Smith and realm NIFI.APACHE.ORG:

```
<authorizer>
    <identifier>file-provider</identifier>
        <identifier>file-provider</identifier>
        <class>org.apache.nifi.authorization.FileAuthorizer</class>
        <property name="Authorizations File">./conf/authorizer</class>
        <property name="Users File">./conf/authorizations.xml<//property>
        <property name="Users File">./conf/users.xml</property>
        <property name="Initial Admin Identity">johnsmith@NIFI.APACHE.ORG</property>
        <property name="Legacy Authorized Users File"></property>
        <property name="Legacy Authorized Users File"></property>
        <property name="Node Identity 1"></property>
        <property name="Node Identity 2"></property>
        <property name="Node Identity 2"></property>
        <property name="Node Identity 2"></property>
        </property>
        <property name="Node Identity 2"></property>
        <property name="Node Identity 2"></property>
        </property>
        <property name="Node Identity 2"></property>
        </property>

        </property name="Node Identity 2"></property>
```

After you have edited and saved the *authorizers.xml* file, restart NiFi. The "Initial Admin Identity" user and administrative policies are added to the *users.xml* and *authorizations.xml* files during restart. Once NiFi starts, the "Initial Admin Identity" user is able to access the UI and begin managing users, groups, and policies.



Note

For a brand new secure flow, providing the "Initial Admin Identity" gives that user access to get into the UI and to manage users, groups and policies. But if that user wants to start modifying the flow, they need to grant themselves policies for the root process group. The system is unable to do this automatically because in a new flow the UUID of the root process group is not permanent until the flow.xml.gz is generated. If the NiFi instance is an upgrade from an existing flow.xml.gz or a 1.x instance going from unsecure to secure, then the "Initial Admin Identity" user is automatically given the privileges to modify the flow.

6.2.2. Legacy Authorized Users (NiFi Instance Upgrade)

If you are upgrading from a 0.x NiFi instance, you can convert your previously configured users and roles to the multi-tenant authorization model. In the *authorizers.xml* file, specify the location of your existing *authorized-users.xml* file in the "Legacy Authorized Users File" property.

Here is an example entry:

```
<authorizers>
    <authorizers>
        <identifier>file-provider</identifier>
        <class>org.apache.nifi.authorization.FileAuthorizer</class>
        <property name="Authorizations File">./conf/authorizer</class>
        <property name="Users File">./conf/authorizations.xml</property>
        <property name="Users File">./conf/users.xml</property>
        <property name="Initial Admin Identity"></property>
        <property name="Legacy Authorized Users File">/Users/johnsmith/
config_files/authorized-users.xml</property>
        </authorizer>
    </authorizer>
</authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer></authorizer>
```

After you have edited and saved the *authorizers.xml* file, restart NiFi. Users and roles from the *authorized-users.xml* file are converted and added as identities and policies in the *users.xml* and *authorizations.xml* files. Once the application starts, users who previously had a legacy Administrator role can access the UI and begin managing users, groups, and policies.

Here is a summary of policies assigned to each legacy role if the NiFi instance has an existing flow.xml.gz:

	Admin	DFM	Monitor	Provenance	NiFi	Proxy
view the UI	*	*	*			
view the controller	*	*	*		*	
modify the controller		*				
view system diagnostics		*	*			
view the dataflow	*	*	*			
modify the dataflow		*				
view the users/groups	*					
modify the users/groups	*					

	Admin	DFM	Monitor	Provenance	NiFi	Proxy
view policies	*					
modify policies	*					
query provenance				*		
access restricted components		*				
view the data		*		*		*
modify the data		*				*
retrieve site-to- site details					*	
send proxy user requests						*

For details on the policies in the table, see Access Policies.

NiFi fails to restart if values exist for both the "Initial Admin Identity" and "Legacy Authorized Users File" properties. You can specify only one of these values to initialize authorizations.

Do not manually edit the *authorizations.xml* file. Create authorizations only during initial setup and afterwards using the NiFi UI.

6.2.3. Cluster Node Identities

If you are running NiFi in a clustered environment, you must specify the identities for each node. The authorization policies required for the nodes to communicate are created during startup.

For example, if you are setting up a 2 node cluster with the following DNs for each node:

```
cn=nifi-1,ou=people,dc=example,dc=com
cn=nifi-2,ou=people,dc=example,dc=com
<authorizer>
        <identifier>file-provider</identifier>
        <class>org.apache.nifi.authorization.FileAuthorizer</class>
        <property name="Authorizations File">./conf/authorizations.xml</
property>
        <property name="Users File">./conf/users.xml</property></property>
        <property name="Initial Admin Identity">johnsmith@NIFI.APACHE.ORG</
property>
        <property name="Legacy Authorized Users File"></property></property>
        cproperty name="Node Identity 1">cn=nifi-1,ou=people,dc=example,dc=
com</property>
        cproperty name="Node Identity 2">cn=nifi-2,ou=people,dc=example,dc=
com</property>
    </authorizer>
</authorizers>
```

In a cluster, all nodes must have the same *authorizations.xml*. If a node has a different *authorizations.xml*, it cannot join the cluster. The only exception is if a node has an empty

).

authorizations.xml. In this scenario, the node inherits the *authorizations.xml* from the cluster.

Now that initial authorizations have been created, additional users, groups and authorizations can be created and managed in the NiFi UI.

6.3. Configuring Users & Access Policies

This section describes:

- How to create users and groups
- How access policies are used to define authorizations
- How to configure access policies by walking through specific examples

Instructions requiring interaction with the UI assume the application is being accessed by User1, a user with administrator privileges, such as the "Initial Admin Identity" user or a converted legacy admin user (see Authorizers.xml Setup).

6.3.1. Creating Users and Groups

From the UI, select "Users" from the Global Menu. This opens a dialog to create and manage users and groups.

14 A C		e—e e—e occo 🖛 💻	5 ×
NiFi Users			
Displaying 1 of 1			
Filter	by user	~	2+
User 🔺			
User1		Member of:	10 %
	t: 11:45:51 EST		

Click the Add icon



To create a user, enter the *Identity* information relevant to the authentication method chosen to secure your NiFi instance. Click OK.

User/Group		
 Individual Group Identity User2 Member of 		
	CANCEL	ок

To create a group, select the "Group" radio button, enter the name of the group and select the users to be included in the group. Click OK.

User/Group		
🔵 Individual 💿 Group		
Identity		
Group_A		
Members		
User1		
✓ User2		
	CANCEL	ок

6.3.2. Access Policies

You can manage the ability for users and groups to view or modify NiFi resources using *access policies*. There are two types of access policies that can be applied to a resource:

- View If a view policy is created for a resource, only the users or groups that are added to that policy are able to see the details of that resource.
- Modify If a resource has a modify policy, only the users or groups that are added to that policy can change the configuration of that resource.

You can create and apply access policies on both global and component levels.

6.3.2.1. Global Access Policies

Global access policies govern the following system level authorizations:

Policy	Privilege	Global Menu Selection
view the UI	Allow users to view the UI	N/A

Policy	Privilege	Global Menu Selection
access the controller	Allows users to view/modify the controller including Reporting Tasks, Controller Services, and Nodes in the Cluster	Controller Settings
query provenance	Allows users to submit a Provenance Search and request Event Lineage	Data Provenance
access restricted components	Allows users to create/modify restricted components assuming otherwise sufficient permissions	N/A
access all policies	Allows users to view/modify the policies for all components	Policies
access users/user groups	Allows users to view/modify the users and user groups	Users
retrieve site-to-site details	Allows other NiFi instances to retrieve Site-To-Site details	N/A
view system diagnostics	Allows users to view System Diagnostics	Summary
proxy user requests	Allows proxy machines to send requests on the behalf of others	N/A
access counters	Allows users to view/modify Counters	Counters

6.3.2.2. Component Level Access Policies

Component level access policies govern the following component level authorizations:

Policy	Privilege
view the component	Allows users to view component configuration details
modify the component	Allows users to modify component configuration details
view the data	Allows user to view metadata and content for this component through provenance data and flowfile queues in outbound connections
modify the data	Allows user to empty flowfile queues in outbound connections and submit replays
view the policies	Allows users to view the list of users who can view/modify a component
modify the policies	Allows users to modify the list of users who can view/ modify a component
retrieve data via site-to-site	Allows a port to receive data from NiFi instances
send data via site-to-site	Allows a port to send data from NiFi instances

You can apply access policies to all component types except connections. Connection authorizations are inferred by the individual access policies on the source and destination components of the connection, as well as the access policy of the process group containing the components. This is discussed in more detail in the Creating a Connection and Editing a Connection examples below.

6.3.2.3. Access Policy Inheritance

An administrator does not need to manually create policies for every component in the dataflow. To reduce the amount of time admins spend on authorization management, policies are inherited from parent resource to child resource. For example, if a user is given access to view and modify a process group, that user can also view and modify the

components in the process group. Policy inheritance enables an administrator to assign policies at one time and have the policies apply throughout the entire dataflow.

You can override an inherited policy (as described in the Moving a Processor example below). Overriding a policy removes the inherited policy, breaking the chain of inheritance from parent to child, and creates a replacement policy to add users as desired. Inherited policies and their users can be restored by deleting the replacement policy.


"View the policies" and "modify the policies" component-level access policies are an exception to this inherited behavior. When a user is added to either policy, they are added to the current list of administrators. They do not override higher level administrators. For this reason, only component specific administrators are displayed for the "view the policies" and "modify the policies" access policies.

You cannot modify the users/groups on an inherited policy. Users and groups can only be added or removed from a parent policy or an override policy.

6.3.3. Access Policy Configuration Examples

The most effective way to understand how to create and apply access policies is to walk through some common examples. The following scenarios assume User1 is an administrator and User2 is a newly added user that has only been given access to the UI.

Let's begin with two processors on the canvas as our starting point: GenerateFlowFile and LogAttribute.



User1 can add components to the dataflow and is able to move, edit and connect all processors. The details and properties of the root process group and processors are visible to User1.

🔢 0 🔲 0 / 0 bytes 💿	0 0 0	0 🔺 2	🏌 0 😂 10:08:12 EST	1 9
🖉 Navigate 🕀				User1
🖞 Operate 🖂	Component	Toolbar Active		
GenerateFlowFile Processor 3132a3d0-0156-1000-0000-000071278711				
0 4 7 × > = = = =				
🕲 🖪 🖉 🗰 delete				
^	A GenerateFlowFile	Configure		
Operate Palette Active	GenerateFlowFile	Status History	LogAttribute	
Operate Palette Active	In 0 (0 bytes)	Status History Upstream connections	In 0 (0 bytes)	5 min
I Operate Palette Active	In 0 (0 bytes) Read/Write 0 bytes / 0 bytes		In 0 (0 bytes) Read/Write 0 bytes / 0 bytes	5 min 5 min 5 min
Operate Palette Active	In 0 (0 bytes)	O Upstream connections	In 0 (0 bytes)	5

User1 wants to maintain their current privileges to the dataflow and its components.

User2 is unable to add components to the dataflow or move, edit, or connect components. The details and properties of the root process group and processors are hidden from User2.

🖽 0 📖 0 / 0 bytes 🔮	0 0 0	0 🛕 2	*0 4	0 10:12:19 EST	1	Q
Navigate 🕀					User2	
Operate 😑	Component Too	Ibar Inactive				
3132a3d0-0156-1000-0000-0000 Processor I2a3d0-0156-1000-0000-000071278711						
Derate Palette Inactive			0 🔺			
	In 0 (0 bytes) Read/Write 0 bytes / 0 bytes	La Status History	In Read/Write	0 (0 bytes) 0 bytes / 0 bytes		5 min 5 min
	Out 0 (0 bytes)	O Upstream connections	Out	0 (0 bytes)		5 min
	Tasks/Time 0/00:00:00.000	Downstream connections & Center in view	Tasks/Time	0 / 00:00:00.000		5 min

6.3.3.1. Moving a Processor

To allow User2 to move the GenerateFlowFile processor in the dataflow and only that processor, User1 performs the following steps:

1. Select the GenerateFlowFile processor so that it is highlighted.

)

2. Select the Access Policies icon



from the Operate palette and the Access Policies dialog opens.

3. Select "modify the component" from the policy drop-down.

howing effective policy inherited from Process	Group NIFI Flow. Override this policy.		
GenerateFlowFile Processor	view the component	~	2+
laer 🔺	view the component	0	
User1	modify the component	0	
	view the data	0	
	modify the data	0	
	receive data via site-to-site	0	
	send data via site-to-site	0	
	view the policies	0	
	modify the policies	0	

The "modify the component" policy that currently exists on the processor (child) is the "modify the component" policy inherited from the root process group (parent) on which User1 has privileges.

4. Select the Override link in the policy inheritance message. When creating the replacement policy, you are given a choice to override with a copy of the inherited policy or an empty policy.

	Access Policies	e—e acca 🖛 🔤 ,	×	
0 0 0	Showing effective policy inherited from Process Group N GenerateFlowFile Processor	Fi Flow. Override this policy. modify the component	20	
3		Override Policy		
		Do you want to override with a copy of the inherited policy or an empty policy? Copy Empty		
		CANCEL OVERSHOE		
,	C Last updated: 10:21:38 EST			

).

Select the Override button to create a copy.

- 1. On the replacement policy that is created, select the Add User icon
 - .

Find or enter User2 in the User Identity field and select OK.

Access Policies		×
C GenerateFlowFile Processor	modify the component	4+ 0
User 🔺		
User1		8
User2		
C Last updated: 10:21:38 EST		

With these changes, User1 maintains the ability to move both processors on the canvas. User2 can now move the GenerateFlowFile processor but cannot move the LogAttribute processor.

nifil 🖸 💩								User	2
🔠 0 🔲 0 / 0 bytes	. 0	0 🦉	▶ 0	0	<mark>▲</mark> 2	* 0	C 10:43:24 EST	1	Q 🖸
 ⊘ Navigate ◇ Operate > 3f32a3d0-0156-1000-0000 > Processor 3f32a3d0-0156-1000-0000 > 3f32a3d0-0156-1000-0000 > Arrowson <	n 3- 2-	In 0 (0 by Read/Write 0 byte Out 0 (0 by Tasks/Time 0 / 00:	tes) s / O bytes tes)	•	5 min 5 min 5 min 5 min			User2	
Original position GenerateFlowFil Processor		······				Out	0 (0 bytes) e 0 bytes / 0 bytes 0 (0 bytes) e 0 / 00:00:00.000		5 min 5 min 5 min 5 min

)

6.3.3.2. Editing a Processor

In the "Moving a Processor" example above, User2 was added to the "modify the component" policy for GenerateFlowFile. Without the ability to view the processor properties, User2 is unable to modify the processor's configuration. In order to edit a component, a user must be on both the "view the component" and "modify the component" policies. To implement this, User1 performs the following steps:

- 1. Select the GenerateFlowFile processor.
- 2. Select the Access Policies icon



from the Operate palette and the Access Policies dialog opens.

3. Select "view the component" from the policy drop-down.

C GenerateFlowFile Processor	view the component 🗸	2+ 1
User 🔺	view the component	
User1	modify the component	
	view the data	
	modify the data	
	receive data via site-to-site 🔹 💿	
	send data via site-to-site 🔹 💿	
	view the policies	
	modify the policies	

The view the component" policy that currently exists on the processor (child) is the "view the component" policy inherited from the root process group (parent) on which User1 has privileges.

- 4. Select the Override link in the policy inheritance message, keep the default of Copy policy and select the Override button.
- 5. On the override policy that is created, select the Add User icon



Find or enter User2 in the User Identity field and select OK.

Access Policies		
O GenerateFlowFile Processor	view the component \checkmark	4 • 1
User =		
User1		
User2		

With these changes, User1 maintains the ability to view and edit the processors on the canvas. User2 can now view and edit the GenerateFlowFile processor.

🔠 0 🔲 0 / 0 bytes	• 0	0 🚿	▶ 0	0	A 2	火 0	C 10:54:56 EST	1	۹
Navigate								User2	
Operate	8		teFlowFile eFlowFile	O Configure	0				
GenerateFlowFile	1 P	n 0 (0 b lead/Write 0 byte		Status Hist					
#32a3d0-0156-1000-0000-0000712787f1		ut 0(0b asks/Time 0/00		-	m connections				
• • • • • • • • • •	-			Usage Change co	or				
🖄 🗈 📓 🖌 🗎 DELETE				Center in v					
^	_			🕗 Сору					
				Delete		0	A		
Operate Palette Active						In	0 (0 bytes)		5 min
							Write 0 bytes / 0 bytes		5 min
						Out	0 (0 bytes)		5 min
						Tasks/	Time 0/00:00:00.000		5 min

6.3.3.3. Creating a Connection

With the access policies configured as discussed in the previous two examples, User1 is able to connect GenerateFlowFile to LogAttribute:

nifi 🗅 🖓	<u>م</u>	ভি	ioi	0 <u>000</u> 0	<u>}</u> ₹⁄				Use	1
🔠 0 🔲 0 / 0 bytes	. 0)	i 🧐	▶ 0	0	<mark>≜</mark> 2	* 0	C 11:05:12 EST	1	۹ 🗉
Ø Navigate	Œ								User1	
👌 Operate	Θ	0		teFlowFile FlowFile						
CenerateFlowFile Processor 3132a3d0-0156-1000-0000-000071278711 C C F K F F F F F F F F F F F F F F F F	2-	Out	0 (0 by Write 0 byte 0 (0 by Time 0 / 00	rs / O bytes ytes)		5 min 5 min 5 min 5 min	Ou	LogAttribute LogAttribute 0 (0 bytes) ad/Write 0 bytes / 0 bytes	, 3	S min S min S min S min
NiFi Flow										

User2 cannot make the connection:

nifil 🖸 🔊 🖬							User	2
🔠 0 🔲 0 / 0 bytes 🦷	0 🔘 0	▶ 0	0	A 2	* 0	C 11:07:11 EST	1	Q 🛛
Ø Navigate ⊕	Generation	teFlowFile eFlowFile					User2	
GenerateFlowFile Processor 2822a340-0156-1000-0000-000071278711 C C F K E C C C C C C C C C C C C C C C C C C	In 0 (0 by Read/Write 0 byte Out 0 (0 by Tasks/Time 0 / 00	rs / 0 bytes ytes)		5 min 5 min 5 min 5 min				
)							
					In Read/Write Out Tasks/Time	0 (0 bytes) 0 bytes / 0 bytes 0 (0 bytes) 0 / 00:00:00.000	0	5 min 5 min 5 min 5 min
401feda4-e293-4118-99ae-8a6d6b72b819								

This is because:

- User2 does not have modify access on the process group.
- Even though User2 has view and modify access to the source component (GenerateFlowFile), User2 does not have an access policy on the destination component (LogAttribute).

To allow User2 to connect GenerateFlowFile to LogAttribute, as User1:

1. Select the root process group. The Operate palette is updated with details for the root process group.

)

).

2. Select the Access Policies icon



from the Operate palette and the Access Policies dialog opens.

3. Select "modify the component" from the policy drop-down.

NiFi Flow Process Group	view the component 🗸	d= (
User =	view the component O	
User1	modify the component	0
	view the data	
	modify the data	
	receive data via site-to-site 🔹 💿	
	send data via site-to-site 💿	
	view the policies	
	modify the policies	

4. Select the Add User icon

(Find or enter User2 and select OK.

Process Group	modify the component 🗸	4+
NiFi Flow Process Group		
User1		0
User2		
Uperz		

By adding User2 to the "modify the component" policy on the process group, User2 is added to the "modify the component" policy on

)

the LogAttribute processor by policy inheritance. To confirm this, highlight the LogAttribute processor and select the Access Policies icon



from the Operate palette:

Access Policies		×
Showing effective policy inherited from Proces	s Group NIFI Flow. Override this policy. modify the component	2+ D
User = User1		
User2		
c c c c c c c c c c c c c c c c c c c		
C Last updated: 11:14:38 EST		

With these changes, User2 can now connect the GenerateFlowFile processor to the LogAttribute processor.

nii 🌢 🖸 🖓	<u>_</u>	छि	joj	0990 8	} ₹				Use	12
🔠 0 🔲 0 / 0 bytes	. 0		0 🖉	▶ 0	0	A 2	淡 0	C 11:17:12 EST	1	Q D
 Navigate Operate 	E	0		ateFlowFile		-			User2	
GenerateFlowFile Processor 3/324340-0156-1000-0000712787/1	2	Out	Vrite 0 byt	bytes) tes / 0 bytes bytes) 0:00:00.000		S min S min S min S min				
							In Read/Wr Out Tasks/Ti	0 (0 bytes) ite 0 bytes / 0 bytes 0 (0 bytes) me 0 / 00:00:00.000	•	5 min 5 min 5 min 5 min
401feda4-e293-4118-99ae-8a6d6b72b	819									

nifil 🖸 🕹 📾	ê <u>i</u> i	• • •		User2
📳 0 🔲 0 / 0 bytes 💿 0	≥ 0 ► 0	■ 0 🔺 2	🕅 🗘 🗘 🔅 🕅 🕅 🕅 🕅	1 9 0
Navigate Derate 68c89018-0158-1000-f351-29cd	GenerateFlowFile GenerateFlowFile In 0 (0 bytes)	5 min		User2
Connection 6669018-0158-1000-f351-29cd70ea03f7 0 4 7 2 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	Read/Write 0 bytes / 0 bytes Out 0 (0 bytes) Tasks/Time 0 / 00:00.00.000	5 min 5 min 5 min 9 Queued 9 (0 byt	es)	
			In 0 (0 bytes) Read/Write 0 bytes / 0 bytes Out 0 (0 bytes) Tasks/Time 0 / 00:00:00.000	5 min 5 min 5 min 5 min 5 min
401feda4-e293-4118-99ae-8a6d6b72b819				

6.3.3.4. Editing a Connection

Assume User1 or User2 adds a ReplaceText processor to the root process group:

🔢 0 🔲 0 / 0 byt	es 💿 O	0 🖌 0 🖉	2 A 1	🌾 0 🛛 11:34:53 EST	Q (
Navigate	æ				
Doperate	Θ	GenerateFlowFile			
NiFi Flow		In 0 (0 bytes)	5 min		
Process Group		Read/Write 0 bytes / 0 bytes	5 min		
101feda4-e293-4118-99ae-8a6d6b7	726819	Out 0 (0 bytes)	5 min		
04 9 1 1	1 2 2	Tasks/Time 0/00:00:00.000	5 min		
عليه فالقا فالع					
20 🖸 🖾 🖌 🗖 🕫	BLETE		Name success		
			Queued 0 (0 bys	es)	
				*	
				LogAttribute	
1	C A Replace	eText		In 0 (0 bytes)	5 min
L	Replace	Text		Read/Write 0 bytes / 0 bytes	5 min
h	n 0(0b	vtes) 5 mi	n	Out 0 (0 bytes)	5 min
		rs / 0 bytes 5 m	n	Tasks/Time 0/00:00:00.000	5 min
,	hut 0 (0 b	ytes) 5 mi	n		

User1 can select and change the existing connection (between GenerateFlowFile to LogAttribute) to now connect GenerateFlowFile to ReplaceText:

nifil 🖸 🖓	<u>مح</u>	তি	<u>i</u> oi	0 <u>000</u>	2-	₹				U	ser1	≡
🔠 0 🔲 0 / 0 bytes	© 0		0 🦉	▶ 0		2	<mark>≜</mark> 1	0	C 11:44:56 EST	1	۹	٦
Navigate	Đ						ш			User1		
Operate	Θ	0		teFlowFile eFlowFile								
Success Connection 68:08:018:0158-1000-f351-29:od70ex03f7 Image: Connection of the second		Out Tasks/T	0 (0 b rite 0 byte 0 (0 b rime 0 / 00 success ed 0 (0 byte	es / 0 bytes ytes) :00:00.000			5 min 5 min 5 min 5 min		LogAttribute			
	Replace	Text	4	ê				In Read/W	0 (0 bytes) rite 0 bytes / 0 bytes		5 mi 5 mi	
In Read/W	0 (0 b) ite 0 byte	s / 0 byte)		5 min 5 min			Out Tasks/T	0 (0 bytes) ime 0 / 00:00:00.000		5 mi 5 mi	
Out Tasks/Ti	0 (0 b) me 0 / 00:	tes)			5 min 5 min							
NiFi Flow												

User 2 is unable to perform this action.

811 O III O /	0 bytes 💿 0	∞ 0 ► 0	2	A 1	× 0	C 11:47:08 EST		Q
Navigate	Œ						User2	
Operate	8	GenerateFlowFile	e					
A01feda4-e293-4	118-99ae-8a6d	In 0 (0 bytes)		5 min				
Process Group		Read/Write 0 bytes / 0 bytes	1	5 min				
01feda4-e293-4118-99ae-8	la6d6b72b819	Out 0 (0 bytes)		5 min				
04 1 1		Tasks/Time 0/00:00:00.000)	5 min				
				Surger .				
46 🖪 🖌	DELETE			Queued 0 (0 byt	(as)	1		
					and the second			
	,					•		
					In	0 (0 bytes)		5 min
						Trite 0 bytes / 0 bytes		5 min
	In 0 (0)	bytes)	5 min		Out	0 (0 bytes)		5 min
	Read/Write 0 byt		5 min		Tasks/1	Time 0/00:00:00.000		5 min
		bytes)	5 min					
	Tasks/Time 0/0	0:00:00.000	5 min					

To allow User2 to connect GenerateFlowFile to ReplaceText, as User1:

- 1. Select the root process group. The Operate palette is updated with details for the root process group.
- 2. Select the Access Policies icon



).

).

3. Select "view the component" from the policy drop-down.

NIFI Flow Process Group	view the component	4+ 1
User .	view the component	
User1	modify the component	
	view the data	
	modify the data	
	receive data via site-to-site 🛛 🛛	
	send data via site-to-site 🛛 💿	
	view the policies	
	modify the policies O	


4. Select the Add User icon

å+

Find or enter User2 and select OK.

Access Policies		×
NIFI Flow Process Group	view the component \checkmark	4+ 0
User .		
User1		0
User2		

Being added to both the view and modify policies for the process group, User2 can now connect the GenerateFlowFile processor to the ReplaceText processor.



7. SAM Authorization

After you have logged in as the streamline user, you can access the SAM UI. The streamline user is assigned the Admin role and can manage users and security permissions. After logging in with this user, go to the menu item Configuration and select Authorizer.

You can use the Authorizer dialog to create users and assign them to roles.

5	Configuration / Authorizer		
æ	USERS ROLES		
43	solson	roles 1	
Ø	streamline-streamanalytics	roles 1	
×	gvetticaden	roles 1	
	harsha	roles 1	
	suresh	roles 1	
	guru	roles 1	
	dan	roles 1	

7.1. Roles and Permissions

SAM provides four out of the box roles which map to the the 3 different personas that SAM provides capabilities for and then a Admin user.

- Admin Role The Admin Role is a super user who has access to all of SAM's system roles and privileges.
- Application Developer Role The Application Developer Role has the privileges necessary to create and submit applications.

- Operations Role The Operations Role has the privileges necessary to create service pools and environments and to submit applications.
- Analyst Role The Analyst Role has access to specific applications and dashboards.
- A role provides permissions (Read, Write, Execute) to 5 different resources in SAM:
- Applications
- Service Pools
- Environments
- User Management / Security
- Dashboards

Table 7.1. Role and Permission Matrix

Resources	Admin Role Access	Application Developer Role Access	Operations Role Access	Analyst Role Access
Streamline Resources	-L	1	1	/
User Mgmt	All Access	No Access	No Access	No Access
Role Mgmt	All Access	No Access	No Access	No Access
Topology	All Access	U: R W X	All: R W X	No Access
Customer Processor	All Access	U: R W	All: R W	No Access
Service Pools	All Access	All: R	All: R W	No Access
Environments	All Access	U: R W	All: R W	No Access
System Artifacts: Notifier UDF UDAF Component Defs Custom Artifacts: Notifier UDF UDAF	All Access (includes edit access to component defs) All Access	Read to All	Read to All	No Access No Access
Dashboards				Has Link to Menu
Schema Registry Reso				
Schemas		All: R W	All: R W	All: -
Model Registry Resou	rces	/	, di. it vv	,
Models	All: R	U: R W		
woulds		0: R W O: R		

7.2. Creating Users and Assigning Them to Roles

Using the streamline user to initially go into SAM, you can create other admin roles in the system that can administer user accounts for the rest of the organization. To create new admin account for user gvetticaden, perform the following steps:

- 1. From Menu, select **Configuration** and then **Authorizer**.
- 2. From the **Users** tab, select the + icon.
- 3. Enter information about the new user account.

5	Configuration / Authorizer	
Å	USERS ROLES	
8 9	New User C	OLES)
Ø	solson R	ROLES
,e	streamline-streamanalytics	OLES
	gvetticaden R	OLES
	harsha R	ROLES
	suresh 1	ROLES
	guru R	ROLES
	dan R	ROLES

4. Click Save.

Result

You are able to see the user you just created in the user list, on the left side of the **SAM Configuration | Authorizer** view.

You do not have to provide any password. This is because SAM relies on a Kerboeros/KDC to do the authentication. The principal is then passed to SAM when accessing the SAM UI. The principal name as part of the kerberos ticket must match a user in SAM. Then SAM looks up the role for that user and provides access based on the roles permissions.

7.3. Sharing Resources

SAM allows users to share different resources with other users to provide a collaborative team environment. A user who has edit access to a resource can share that resource with another user. When a resource is shared, the user can configure if the resource being shared can be just viewed or edited.

SAM allows the following resources to be shared:

- Environments
- Applications

7.3.1. Sharing an Environment

About This Task

By default, only the user who created an environment can see that environment. However, it is common for environments to be shared amongst a group of users. To do this, the user who created the environment must share that environment with other users.

Steps

- 1. From the left-hand menu select **Configuration**, then **Environment**.
- 2. From the environment you want to share, click the **Configuration** elipses at the top right and click **Share**.
- 3. In the **Share Environment** dialog, select the users with whom you want to share the environment.
- 4. Specify whether you want to give them **View** or **Edit** privileges and click **Ok**.

7.4. Sharing an Application

About This Task

By default, only the user who created an application can see that it. However, it is common for applications to be shared amongst a group of users. To do this, the user who created the application must share that it with other users.

Steps

- 1. From the left-hand menu select My Applications.
- 2. From the application you want to share, click the **Configuration** elipses at the top right and click **Share**.

- 3. In the **Share Application** dialog, select the users with whom you want to share the application.
- 4. Specify whether you want to give them **View** or **Edit** privileges and click **Ok**.

7.5. SAM Authorization Limitations

- SAM's roles and access control policies are maintained in SAM. Ranger support for SAM is not available in HDF 3.0.
- Creation of users and assignment to roles must be done using the SAM UI. In the HDF 3.0 release, there is no support to import users from KDC/AD.
- Role assignment is at a user level. Assigning roles to a group is not supported in HDF 3.0 release.
- New Roles or editing the out of the box role cannot be allows. However, the collaboration sharing features allow you to share each of the 5 resources across users meeting most use case requirements.

8. Deploying SAM Applications in a Secure Cluster

In a secure/kerberized env, SAM will deploy an application to kerberized Storm cluster and that app has to talk to secure services (e.g: Secure Kafka, HBase, HDFS, Hive, etc..). Deploying secure streaming apps that talks to secure services has been traditionally very difficult to configure. SAM makes it considerably easier to deploy secure streaming apps.

8.1. Connecting to a Secure Service that Supports Delegation Tokens

About This Task

SAM uses *delegation tokens* when possible, when talking to secure streaming services. The concept of delegation token is introduced to avoid frequent authentication checks against Kerberos(AD/MIT). After the initial authentication against Namenode using Kerberos, subsequent authentication are done without a Kerberos service ticket(TGT). Once the client authentication with Kerberos for Namenode is successful, the client receives a delegation token from the Namenode. This token has an expiration and max issue date but can be reviewed.

A delegation token is secret key shared with the Storm/NameNode/HBase which provides a mechanism for Storm/NameNode/HBase to impersonate a user to perform an operation. Delegation tokens are supported for the following services: Storm, HDFS, Hive, HBase.

You can use Storm's Nimbus service to get delegation tokens on behalf of the topology submitter user. Nimbus can get HDFS, HBase and other delegation tokens associated with the user who submitted the topology and can push it to the users stream application. This decreases operational/deployment complexity because you do not have to distribute keytabs to all possible key tabs.

Example

If your application is going to interact with secure HBase, your bolts/states needs to be authenticated by HBase. Typically, you are required to have storm.keytab.file on all the potential worker hosts. If you have multiple topologies on a cluster, each with different user, you will have to create multiple keytabs and distribute it to all workers.

With SAM, you can configure Nimbus to automatically get delegation tokens on behalf of the topology submitter user. To do this in SAM, you can configure a single principal and keytab in SAM for a given application and this principal is used by Nimbus to impersonate the user/app. The only requirement is that the keytab for this principal must reside on the host where Nimbus is located. To configure this single principal that will be used by Nimbus to impersonate the user/app when connecing to secure big data services like HBase, HDFS, Hive, do the following:

Steps

1. Click into your stream application, and then click Edit.

2. Click the **Configure** icon () located on top right of the stream application.

- 3. Select the **Security** tab.
- 4. Select the principal and and Keytab path. SAM automatically populates all the principal and key tabs located on the Nimbus Host to make this easier. Then click **Ok**.

pplication Configuration	2
ENERAL SECURITY ADVANCED	
Clusters Security Config +	
CLUSTER NAME *	面
streamanalytics	-
PRINCIPAL *	
storm-streamanalytics@STREAMANALYTICS	-
KEYTAB PATH *	
/etc/security/keytabs/storm.headless.keytab	

Result

When user X deploys the application, Nimbus uses the principal and the keytab configured above to impersonate user X when interacting with the big data services in the application.

8.2. Connecting to Secure Kafka

About This Task

Kafka does not support delegation tokens. You must configure the Kafka source/sink processor with the principal and keytab used to authenticate the stream applications with Kafka. Use these steps to configure SAM to communication with a secure Kafka service.

Steps

- 1. Double click on the Kafka source/sink component on the canvas.
- 2. Select the **Security** tab.
- 3. Configure the Kerberos client principal, Kerberos keytab file, and the Kafka service name. The client principal and keytab selected must exist on all the worker nodes in the cluster. Using the storm-<cluster-name> principal is recommended because Ambari creates that keytab on each worker node when running the Ambari Kerberos Wizard . Set the Kafka service name to "kafka".

×

TruckSpeedEvent

REQUIRED SECURITY OPTIONAL NOTES	
KERBEROS CLIENT PRINCIPAL *	Output
storm-streamanalytics@STREAMANALYTICS	eventTime*
KERBEROS KEYTAB FILE *	eventSource* string truckId*
KAFKA SERVICE NAME *	NTEGER driverid* NTEGER
kafka	driverName* string
SSL KEYSTORE LOCATION	routeld*
SSL KEYSTORE PASSWORD	INTEGER
SSL KEY PASSWORD	
	Cancel Ok

8.3. Securing SAM – An End-to-End Workflow


To help understand how all of this fits together, let's walk through a use case to see how SAM to deploys applications in a secure cluster.

The use case details are the following:

- An organization has a secure HDF/HDP cluster and all cluster services have been kerborized.
- User gvetticaden is a developer and part of the release engineering team, builds a streaming application that includes of the following capabilities:
 - Creating streams from a set of Kafka topics from a secure Kafka Broker.
 - Doing analytics on the stream.
 - Persisting different events to following secure data stores: HDFS, HBase, HIve
- User gvetticaden wants to deploy the streaming application to a secure storm Service.

8.3.1. Understanding the End-to-End Workflow

The below image provides an explanation on how SAM functions for the above use case.



Step 1: Initial Login

User gvetticaden authenticates himself to the organization AD/KDC by doing a kinit. Typically in an organization, the ticket is granted when the user logs into the corporate LAN.

Principal/Keytab Used to Connct: gvetticaden

Step 2: SAM Grants Access Based on Roles and Permissions

SAM looks up the roles for gvetticaden. Based on the permissions associated with the roles, SAM gives gvetticaden access to specific features.

Step 3a: Build and Deploy a Streaming Application

User gvetticaden builds the streaming analytics application and deploys it. The application includes the following capabilities:

- Creating streams from a set of Kafka topics from a secure Kafka Broker.
- Doing analytics on the stream.
- Persisting different events to following secure data stores: HDFS, HBase, HIve

Step 3b: SAM Communicates with Storm

SAM communicates with Storm Streaming Engine to deploy the stream application using the streamline principal/keyab. SAM is functioning as a client submitting a job to Secure Storm. The internal streamline user will impersonate gvetticaden when it talks to Storm. Hence ACLs within Ranger for Storm can be configured for gvetticaden, the person deploying the streaming application.

Principal/Keytab Used to Connect: The streamline principal/keytab is used to connect, and user gvetticaden is impersonated.

Step 4: Communication with Secured Big Data Services

When SAM deploys the application, it passes the application principal and keytab to Nimbus. Nimbus uses this principal to authenticate to big data services that support tokens. The principal impersonates gvetticaden. The result is that all Ranger ACLs for HBase, Hive, and HDFS are configured for gvetticadne, the user deploying the streaming application.

Step 5: Communication with Secured Big Data Services that do not Support Delegation Tokens

If the application uses a Kafka Source or Sink, then the application uses the principal and keytab configured under the Kafka component security settings.

Principal/Keytab Used to Connect:: The principal/keytab configured in Kafka are used to connect.