

Securing Cloudera Edge Management

Date published: 2019-04-15

Date modified: 2025-02-28

CLOUDERA

Legal Notice

© Cloudera Inc. 2025. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER'S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

Cloudera Edge Management security overview.....	4
Identity mapping.....	4
TLS configuration for Cloudera Edge Management.....	5
TLS keys and certificates.....	5
TLS key and certificate examples.....	6
TLS configuration for EFM.....	8
Agent authentication.....	10
User authentication.....	10
Configuring OpenID Connect SSO.....	12
Configuring SAML 2.0 SSO.....	13
Configuring Knox SSO.....	15
Configuring mutual TLS authentication.....	16
Configuring proxy authentication.....	17
Configuring LDAP authentication.....	18
Access control policies.....	19
Access control bootstrapping.....	20
Initial admin identities.....	20
First login with a new user.....	21
User management.....	22
Creating users.....	23
Editing users.....	23
User group management.....	24
Creating user groups.....	24
Editing user groups.....	25
Managing user groups using IdP.....	27
Managing user groups using LDAP.....	28
Agent class roles policies.....	31
Assigning policies to a user.....	34
Assigning policies to a user group.....	35
Assigning policies to agent classes.....	37
SSO identity provider setup.....	40
Okta integration using OIDC.....	40
Okta Edge Flow Manager integration using SAML.....	41

Cloudera Edge Management security overview

Cloudera Edge Management is not secure by default. Cloudera recommends that you must always enable security for production environment. To secure Cloudera Edge Management, you must secure both Edge Flow Manager and MiNiFi agents.

By default, Edge Flow Manager runs in an unsecured mode where the web endpoints are accessible over HTTP on all network interfaces and clients are not authenticated. When unsecured, all clients are anonymous and have full access to the application. For this reason, insecure mode should only be used for test or development purposes and when Edge Flow Manager is not accessible through the public Internet.

Limiting the network interfaces that the web server binds to is configurable in the efm.properties file.

```
efm.web.host=localhost
```

For production environments, security should always be enabled by configuring a TLS context and method of user authentication.

Securing Cloudera Edge Management involves securing both the Edge Flow Manager server and MiNiFi agents.

The Edge Flow Manager server provides centralized control of MiNiFi agents. Starting with version 1.3.0, Edge Flow Manager provides robust options for authentication and authorization.

The high-level steps for securing a Cloudera Edge Management system are:

1. Generating or obtaining keys and certificates for Edge Flow Manager, MiNiFi agents, and optionally service user accounts.
2. Configuring the Edge Flow Manager TLS context.
3. Configuring MiNiFi agent TLS contexts, which allows MiNiFi agents to authenticate to a secured Edge Flow Manager server.
4. Configuring end-user authentication for the Edge Flow Manager web application UI, typically as an integration with a Single Sign On (SSO) identity provider.
5. Assigning access control policies to users and groups in the Edge Flow Manager web application UI.

For more information about the security aspects of Edge Flow Manager, check out the video on the Cloudera Edge Management YouTube playlist:<https://www.youtube.com/embed/KOc9YKfwZYE>

Identity mapping

Identity mapping allows you to normalize user and group identities from different identity providers.

For example, you can combine mTLS authentication with an LDAP user group manager, even if there is no exact match in the Distinguished Name (DN) from the user certificate and LDAP.

The following examples demonstrate normalizing DNs from certificates and LDAP:

Certificate DN mapping

- efm.security.identity.mapping.pattern.dn=[^]CN=(.*?), OU=(.*?), O=(.*?), L=(.*?), ST=(.*?), C=(.*?)\$
- efm.security.identity.mapping.value.dn=\$1
- efm.security.identity.mapping.transform.dn=LOWER

LDAP DN mapping

- efm.security.identity.mapping.pattern.ldap=[^]cn=(.*?), ou=(.*?), o=(.*?)\$
- efm.security.identity.mapping.value.ldap=\$1
- efm.security.identity.mapping.transform.ldap=LOWER

Each property's final segment serves as an identifier, linking the pattern to the replacement value. When a user initiates a request in Edge Flow Manager, their identity is verified against these patterns in lexicographical order. When encountering the first matching pattern, the replacement specified in the `efm.security.identity.mapping.value.xxxx` property is applied.

For instance, when a login with the DN "CN=admin, OU=EFM, O=Cloudera, L=Santa Clara, ST=CA, C=US" corresponds to the above DN mapping pattern, the DN mapping value of "\$1" is used, normalizing the user to localhost.

The LDAP DN is slightly different so it would not match with the certificate identity. To resolve this issue, a pattern is applied, to extract the CN part of the LDAP's DN and transform the value to lowercase.

In addition to mapping, there is an option to apply transformations. Supported transformation options include:

- **NONE**: no transformation is applied
- **LOWER**: identity is converted to lowercase
- **UPPER**: identity is converted to uppercase

If not specified, the default value is **NONE**.

Group names can also be mapped. The following example accepts the existing group name but converts it to uppercase:

Group name mapping

- `efm.security.group.mapping.pattern.dn=^(.*)_*`
- `efm.security.group.mapping.value.dn=$1`
- `efm.security.group.mapping.transform.dn=UPPER`



Note: These mappings are also applied to the User and Group Initial Admin Identities.

TLS configuration for Cloudera Edge Management

To secure Cloudera Edge Management, learn how to secure your Edge Flow Manager server and MiNiFi agents through TLS. Also learn about the TLS keys and certificates needed for these tasks.

TLS keys and certificates

When using Cloudera Edge Management, sensitive information is sent over the network between Edge Flow Manager and MiNiFi agents including configuration files that contain passwords. To secure this transfer, you must configure Transport Layer Security (TLS) encryption.

TLS is an industry standard set of cryptographic protocols for securing communications over a network.

Configuring TLS involves creating a private key and a public key for use by server and client processes to negotiate an encrypted connection. In addition, TLS can use certificates to verify the trustworthiness of keys presented during the negotiation to prevent spoofing and mitigate other potential security issues.

Because TLS keys and certificates are usually specific to each enterprise organization, Cloudera Edge Management needs these details manually configured.

To secure Cloudera Edge Management through TLS, you need the following:

- A Certificate Authority (CA) or intermediate signing authority public certificate, used to sign certificates and verify trust. Edge Flow Manager uses this certificate in its truststore in order to verify the identity of MiNiFi agents by validating their certificates. MiNiFi agents use this certificate in their truststores in order to verify the identity of the Edge Flow Manager servers by validating their certificates.

- A public and private keypair for Edge Flow Manager signed by the CA, recommended one per host when doing a cluster deployment.
- A public and private keypair for MiNiFi agents signed by the CA, recommended one per agent.

Before configuring TLS, ensure that the certificates used meet the requirements.

Certificate requirements

- The Edge Flow Manager KeyStore must be in Java KeyStore (JKS) or PKCS #12 (PKCS12 aka .p12) format.
- The Edge Flow Manager KeyStore can contain one or more private key entries. If multiple entries are used, Edge Flow Manager must be configured accordingly. For more information, see *TLS configuration for Edge Flow Manager*.
- The X509v3 KeyUsage section of the certificate must include the following attributes:
 - DigitalSignature
 - Key_Encipherment
- The X509v3 ExtendedKeyUsages section of EFM and MiNiFi agent certificates must include the following attributes:
 - clientAuth
 - serverAuth
- The signature algorithm used for certificates must be sha256WithRSAEncryption (SHA-256).
- For Edge Flow Manager certificates, Subject Alternate Names (SANs) are mandatory and should at least include the FQDN of the host.
- Additional names for the certificate and host can be added to the certificate as SANs.
 - Add the FQDN used for the Common Name (CN) as a DNS SAN entry.
 - If you are planning to use a load balancer for an Edge Flow Manager cluster, include the FQDN for the load balancer as a DNS SAN entry.

Cloudera recommends the following security protocols:

- Use certificates that are signed by a CA. Do not issue self-signed certificates.
- Generate a unique certificate per host, including MiNiFi agents. Do not use wildcard certificates.

Related Information

[TLS configuration for Edge Flow Manager](#)

[TLS key and certificate examples](#)

TLS key and certificate examples

Review the following examples to understand how to implement Transport Layer Security (TLS) encryption in Cloudera Edge Management.

Prerequisites

You need a Root Certificate Authority (CA) to sign the generated certificates. If you do not have one, it can be generated. Cloudera does not recommend using self-signed certificates for production environments.

```
openssl genrsa -out root.key
openssl req -new -x509 -key root.key -out root.crt
```

Example 1 - Generating Edge Flow Manager certificates with one private key entry

Use the following commands to generate a keystore and a truststore for Edge Flow Manager with a single private key entry. Use a secure password and change the dname and the SAN entry of the certificate to match your specific use case.

```
keytool -keystore efm_keystore.pkcs12 -keypass changeIt -storepass changeIt
-alias server -validity 365 -genkey -keyalg RSA -ext SAN=dns:node1.example.com -dname "CN=node1"
```

```
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias server -cer
treq -file server.unsigned.crt -ext SAN=dns:node1.example.com
openssl x509 -req -CA root.crt -CAkey root.key -in server.unsigned.crt -out
server.signed.crt -days 365 -CAcreateserial -copy_extensions copyall
```

```
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias CARoot -imp
ort -file root.crt
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias server -
import -file server.signed.crt
```

```
keytool -keystore efm_truststore.pkcs12 -keypass changeIt -storepass changeIt
-alias CARoot -import -file root.crt
```

Example 2 - Generating Edge Flow Manager certificates with two private key entries

Use the following commands to generate a keystore and a truststore for Edge Flow Manager with multiple private key entries: one for the Edge Flow Manager - WEB communication (server) and one for Edge Flow Manager internal communication (service). Use a secure password and change the dname and the SAN entry of the certificate to match your specific use case.

```
keytool -keystore efm_keystore.pkcs12 -keypass changeIt -storepass changeIt
-alias server -validity 365 -genkey -keyalg RSA -ext SAN=dns:node1.example.com -dname "CN=node1"
keytool -keystore efm_keystore.pkcs12 -keypass changeIt -storepass changeIt
-alias service -validity 365 -genkey -keyalg RSA -dname "CN=service"
```

```
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias server -cer
treq -file server.unsigned.crt -ext SAN=dns:node1.example.com
openssl x509 -req -CA root.crt -CAkey root.key -in server.unsigned.crt -out
server.signed.crt -days 365 -CAcreateserial -copy_extensions copyall
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias service -
certreq -file service.unsigned.crt
openssl x509 -req -CA root.crt -CAkey root.key -in service.unsigned.crt -out
service.signed.crt -days 365 -CAcreateserial -copy_extensions copyall
```

```
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias CARoot -imp
ort -file root.crt
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias server -
import -file server.signed.crt
keytool -keystore efm_keystore.pkcs12 -storepass changeIt -alias service -
import -file service.signed.crt
```

```
keytool -keystore efm_truststore.pkcs12 -keypass changeIt -storepass test123
4 -alias CARoot -import -file root.crt
```

Example 3 - Generating agent certificates

Use the following commands to generate a keystore and a truststore for agents with a single private key entry. Use a secure password and change the dname and the SAN entry of the certificate to match your specific use case.

```
keytool -keystore agent_keystore.pkcs12 -keypass changeIt -storepass changeIt -alias agent -validity 365 -genkey -keyalg RSA -ext SAN=dns:agent.example.com -dname "CN=agent"
```

```
keytool -keystore agent_keystore.pkcs12 -storepass changeIt -alias agent -certreq -file agent.unsigned.cert -ext SAN=dns:agent.example.com
openssl x509 -req -CA root.crt -CAkey root.key -in agent.unsigned.cert -out agent.signed.cert -days 365 -CAcreateserial -copy_extensions copyall
```

```
keytool -keystore agent_keystore.pkcs12 -storepass changeIt -alias CARoot -import -file root.crt
keytool -keystore agent_keystore.pkcs12 -storepass changeIt -alias agent -import -file agent.signed.cert
```

```
keytool -keystore agent_truststore.pkcs12 -keypass changeIt -storepass test1234 -alias CARoot -import -file root.crt
```

TLS configuration for EFM

Learn about the properties that you need to set to configure TLS for Edge Flow Manager.

When TLS is disabled, Edge Flow Manager runs in an unsecured mode where the web endpoints are accessible over HTTP on all network interfaces and clients are not authenticated. When unsecured, all clients are anonymous and have full access to the application. For this reason, insecure mode should only be used for test or development purposes and when Edge Flow Manager is not accessible through the public Internet.

Limiting the network interfaces that the web server binds to is configurable in the efm.properties file.

```
efm.web.host=localhost
```

For production environments, security should always be enabled by configuring a TLS context and method of user authentication.

Securing an Edge Flow Manager instance starts with configuring a TLS context, also known as an SSL context. Enabling TLS enforces that all usage of the Edge Flow Manager web application as well as agent communication is authenticated and that the authenticated user or agent is allowed to perform requested actions based on policies.

Settings for the Edge Flow Manager TLS context are configured using the efm.server.ssl.* prefixed properties in the efm.properties file:

```
efm.server.ssl.enabled=true
efm.server.ssl.keyStore=/path/to/keystore.jks
efm.server.ssl.keyStoreType=jks
efm.server.ssl.keyStorePassword=keyStorePassword
efm.server.ssl.keyPassword=keyPassword
efm.server.ssl.trustStore=/path/to/truststore.jks
efm.server.ssl.trustStoreType=jks
efm.server.ssl.trustStorePassword=trustStorePassword
efm.server.ssl.clientAuth=WANT
efm.server.ssl.keyAlias=
efm.server.serviceUserKeyAlias=
```

Where,

- `efm.server.ssl.enabled`
Set to true to enable TLS and secure Edge Flow Manager.
- `efm.server.ssl.keyStore`
The file path to the keystore containing the Edge Flow Manager TLS keypair.
- `efm.server.ssl.keyStoreType`
Set to jks or pkcs12 depending on the format of the keystore. Other formats are not supported.
- `efm.server.ssl.keyStorePassword`
The passphrase for the keystore.
- `efm.server.ssl.keyPassword`
The passphrase for the key in the keystore.
- `efm.server.ssl.trustStore`
The file path to the truststore containing the public certificates of the Certificate Authorities (CA) trusted by Edge Flow Manager.
- `efm.server.ssl.trustStoreType`
Set to jks or pkcs12 depending on the format of the truststore. Other formats are not supported.
- `efm.server.ssl.trustStorePassword`
The passphrase for the truststore.
- `efm.server.ssl.clientAuth`
Set to WANT to allow MiNiFi agents to authenticate to Edge Flow Manager with TLS client certificates, but allow users to use an alternative form of authentication (such as SSO). If users are also using mutual TLS with client certificates in browsers, then this can be set to NEED.
- `efm.server.ssl.keyAlias` and `efm.server.serviceUserKeyAlias`
 - If you have a keystore with a single private key entry (see Example 1 from the TLS key and certificate examples), leave `efm.server.ssl.keyAlias` and `efm.server.serviceUserKeyAlias` commented out.
 - If you have a keystore with multiple elements, for example separate keys for Edge Flow Manager internal and external SSL communication (see Example 2 from the TLS key and certificate examples), set both of these properties.
 - If you have a keystore with multiple private key entries, configure the properties as follows:
 - `efm.server.ssl.keyAlias=server`
 - `efm.server.serviceUserKeyAlias=service`

**Note:**

The default cluster communication port for Infinispan is 7800. You can configure it using the `efm.infinispan.jgroups[bind.port].tcp.port` property value.

The default cluster communication port for Resource Manager Synchronization is 9010. You can configure it using the `efm.resourcemanager.resourceManagerPort` property value.



Note: When efm.server.ssl.enable is enabled and Edge Flow Manager is operating in clustered mode (efm.cluster.enabled=true), you must configure efm.security.user.auth.serviceIdentities to enable intra-cluster communication used by the resource manager synchronization.

- If you have a keystore with a single private key entry (see Example 1 from the TLS key and certificate examples), use the dname of the certificates to populate the property. Assuming each node has a different certificate:
 - efm.security.user.auth.serviceIdentities[0]=CN=node1
 - efm.security.user.auth.serviceIdentities[1]=CN=node2
 - efm.security.user.auth.serviceIdentities[2]=CN=node3
- If you have a keystore with multiple elements, for example separate keys for Edge Flow Manager internal and external SSL communication (see Example 1 from the TLS key and certificate examples), use the dname of the certificate. In this case one entry will likely be enough as it is not necessary to create a node-specific dname for the service user: efm.security.user.auth.serviceIdentities[0]=CN=service



Note: For a clustered deployment, these properties must be set on every node in the Edge Flow Manager cluster.

Related Information

- [TLS keys and certificates](#)
- [TLS key and certificate examples](#)

Agent authentication

Learn about the properties that you need to set to configure TLS for MiNiFi agents.

When TLS is enabled to secure Edge Flow Manager, agents must be authenticated using client certificates. Client certificates are trusted if the Certificate Authority and any intermediate signing authorities (if applicable) are present in the Edge Flow Manager truststore configured as described in *TLS configuration for Edge Flow Manager*.

For more information on requirements for MiNiFi agent client certificates and instructions for generating new certificates, see *TLS keys and certificates*.

Cloudera recommends using a unique client certificate per agent. However, it is not a requirement.

For details about the properties that you need to set to configure TLS for MiNiFi agents, see *MiNiFi C++ agent authentication* and *MiNiFi Java agent authentication*.

Related Information

- [TLS configuration for Edge Flow Manager](#)
- [TLS keys and certificates](#)
- [Integrating with the Windows certificate store](#)
- [MiNiFi C++ agent authentication](#)
- [MiNiFi Java agent authentication](#)

User authentication

You can secure Edge Flow Manager by integrating with Single Sign-On (SSO) identity providers for login purposes. You can also manage user roles to control access to agent classes and authorized actions. Learn about the properties that you need to configure to enable user authentication within Edge Flow Manager.

Securing Edge Flow Manager requires a reliable authentication mechanism for users. Edge Flow Manager supports the following authentication methods:

- SSO integration with an identity provider using SAML 2.0

- SSO integration with an identity provider using OpenID Connect (OIDC)
- SSO with Apache Knox (using Knox as a gateway is not possible)
- Mutual TLS (mTLS) authentication with client certificates
- Proxy authentication
- LDAP authentication

Integrating with an SSO identity provider using OIDC or SAML is the preferred approach for authenticating users. If OIDC is available, Cloudera recommends it as it is usually the easiest to configure and administer.

For service accounts, such as those that programmatically interact with the Edge Flow Manager RESTful API for automation or monitoring purpose, mutual TLS authentication must be used, and can be enabled in addition to another mechanism such as one of the SSO login options.

MiNiFi agents use a different method of authenticating to Edge Flow Manager not controlled by these properties. For more information on MiNiFi agent authentication, see *Agent authentication*.

You need to set the following properties that are shared by all user authentication methods:

```
# User Authentication Properties
efm.security.user.auth.enabled=true
efm.security.user.auth.adminIdentities=admin
efm.security.user.auth.autoRegisterNewUsers=true
efm.security.user.auth.authTokenExpiration=12h
```

Where,

- efm.security.user.auth.enabled

Set to true to enable user authentication in Edge Flow Manager. You must also enable a specific method of authentication (oidc|saml|knox|certificate|proxy) when user authentication is enabled.

- efm.security.user.auth.adminIdentities

A comma separated list of identities needed for initial admins that can configure other user and group access policies in Edge Flow Manager. For more information on initial admins, see *Access control bootstrapping*.

If admin identities contain special characters such as a comma (,), then this alternative property key format can be used:

- efm.security.user.auth.adminIdentities[0]=CN=admin1, OU=systems, O=cloudera
- efm.security.user.auth.adminIdentities[1]=CN=admin2, OU=systems, O=cloudera
- ...
- efm.security.user.auth.adminIdentities[n]=CN=adminN, OU=systems, O=cloudera
- efm.security.user.auth.autoRegisterNewUsers

With SAML or OIDC, Edge Flow Manager can optionally create user accounts for authenticated users automatically the first time that they log into Edge Flow Manager, rather than users needing to be explicitly created in Edge Flow Manager prior to first login. Set to true to enable this feature.



Note: Knox, mTLS, and Proxy authentication methods do not support this feature and ignore this property.

- efm.security.user.auth.authTokenExpiration

With SAML, OIDC, or LDAP, Edge Flow Manager issues access tokens once a user is authenticated. This property specifies the duration for which the token is valid.



Note: Knox, mTLS, and Proxy authentication methods do not issue access tokens and ignores this property.

Related Information

[Agent authentication](#)

[Access control bootstrapping](#)

Configuring OpenID Connect SSO

Edge Flow Manager supports OpenID Connect (OIDC), an industry standard for using a third party as an identity provider for web applications. Learn about the properties that you need to set for configuring OIDC SSO.

OIDC is sometimes referred to as OAuth 2 login because it is an authentication protocol that extends the authorization protocols in OAuth 2. In the terminology of OIDC, Edge Flow Manager is the Relying Party and the SSO identity provider is the OpenID Provider.

Before configuring Edge Flow Manager, you should first set up an OIDC client application configuration in your SSO identity provider. For more information about how to do this, see *SSO identity provider setup*.

Before configuring OIDC, Edge Flow Manager should already be configured to use TLS. OIDC authentication requires passing an access token to Edge Flow Manager that is vulnerable to compromise if TLS is not enabled, and therefore Edge Flow Manager does not allow using OIDC authentication without TLS enabled. For more information on enabling TLS in Edge Flow Manager, see *TLS configuration for Edge Flow Manager*.



Note: To use OIDC in a clustered Edge Flow Manager environment, sticky sessions should be enabled in the Edge Flow Manager load balancer.

To enable OIDC in Edge Flow Manager, configure the following properties in the efm.properties file:

```
efm.security.user.oidc.enabled=true
efm.security.user.oidc.issuerUri=https://example.okta.com/oauth2
efm.security.user.oidc.clientId=efm
efm.security.user.oidc.clientSecret=abc123...
efm.security.user.oidc.scopes=profile,email,groups
efm.security.user.oidc.usernameAttribute=email
efm.security.user.oidc.displayNameAttribute=name
efm.security.user.oidc.groupAttribute=groups
```

Where,

- efm.security.user.oidc.enabled
Set to true to enable OIDC authentication.
- efm.security.user.oidc.issuerUri
The OpenID Provider base URI. Consult your OpenID Provider documentation for the correct value.
- efm.security.user.oidc.clientId
It must match the configured client application name from the OpenID Provider.
- efm.security.user.oidc.clientSecret
It must match the configured client secret from the OpenID Provider.
- efm.security.user.oidc.scopes
It controls what user attributes are provided from the OpenID Provider to Edge Flow Manager when the user authenticates.
- efm.security.user.oidc.usernameAttribute
It controls which of the user attributes provided to Edge Flow Manager from the OpenID Provider is used as the Edge Flow Manager User identity. Typically this is the email address attribute.
- efm.security.user.oidc.displayNameAttribute
If this property is provided and efm.security.user.auth.autoRegisterNewUsers is enabled, it controls which user attribute is mapped to the Edge Flow Manager User Display Name field when the user first logs into Edge Flow Manager.
- efm.security.user.oidc.groupAttribute
It must match the configured Group Claim Name from the OpenID Provider.

Edge Flow Manager supports OpenID Connect Discovery as a way to discover additional details it needs directly from the OpenID Provider. For this to work, the OpenID Provider must host a discovery endpoint at `{issuerUri}/well-known/openid-configuration`. This is supported by all major, modern SSO vendors offering OpenID Connect. If this endpoint is not available over the network at runtime, Edge Flow Manager fails to start. If this is not possible in your environment, Edge Flow Manager offers a set of staticConfig properties, that you need to configure, as an alternative to OpenID Connect Discovery over the network:

```
efm.security.user.oidc.staticConfig.enabled=false
efm.security.user.oidc.staticConfig.authorizationUri=
efm.security.user.oidc.staticConfig.tokenUri=
efm.security.user.oidc.staticConfig.userInfoUri=
efm.security.user.oidc.staticConfig.jwkSetUri=
```

When these properties are enabled, OpenID Connect Discovery is not performed. So, these act as an override for configuration that would normally be dynamically discovered. The correct values to use can be provided by the OpenID Provider.

Related Information

[SSO identity provider setup](#)

[TLS configuration for Edge Flow Manager](#)

Configuring SAML 2.0 SSO

Learn about the properties that you need to set for configuring SAML 2.0 SSO.

Before configuring Edge Flow Manager to use SAML, you should first set up an SAML client application configuration in your SSO identity provider. For information about how to do this, see [SSO identity provider setup](#).

Before configuring SAML, Edge Flow Manager should already be configured to use TLS. SAML authentication requires passing an access token to Edge Flow Manager that is vulnerable to compromise if TLS is not enabled, and therefore Edge Flow Manager does not allow using SAML authentication without TLS enabled. For more information on enabling TLS in Edge Flow Manager, see [TLS configuration for Edge Flow Manager](#).

Edge Flow Manager supports Identity Provider (IdP) and Service Provider (SP) initiated flow.

To enable SAML in Edge Flow Manager, the following properties must be set in the `efm.properties` file:

```
efm.security.user.saml.enabled=true
efm.security.user.saml.metadataLocation=https://example.okta.com/app/example
/sso/saml/metadata
efm.security.user.saml.groupAttribute=groups
```

Where,

- `efm.security.user.saml.enabled`
Set to true to enable SAML authentication.
- `efm.security.user.saml.metadataLocation`
Identity provider metadata location that is used for dynamic configuration.
- `efm.security.user.saml.groupAttribute`
The name of a SAML assertion attribute containing group names the user belongs to.



Note: With default configuration, Audience URI (SP Entity ID) is `{baseUrl}/saml2/serviceProviderMetadata/efmSaml`, where `baseUrl` depends on the server configuration. Example Entity ID: `https://localhost:10090/efm/saml2/serviceProviderMetadata/efmSaml`.

Optional parameters for further configuration are as follows:

```
efm.security.user.saml.entityId=efmCustomEntityId
```

```
efm.security.user.saml.signingCredentials.privateKeyLocation=/path/to/private.key
efm.security.user.saml.signingCredentials.privateKeyPassword=password
efm.security.user.saml.signingCredentials.certificateLocation=/path/to/certificate.crt
efm.security.user.saml.displayNameAttribute=displayNameAttribute
```

Where,

- efm.security.user.saml.entityId

The application-defined unique identifier that is the intended audience of the SAML assertion. It is advisable to use this property when the default {baseUrl} dependent Entity ID is undesirable.



Note: You must ensure that the Entity ID value matches the value configured for your Identity Provider's Audience URI (SP Entity ID).

- efm.security.user.saml.signingCredentials.privateKeyLocation
Private key location for signing SAML request.
- efm.security.user.saml.signingCredentials.privateKeyPassword
Private key password.
- efm.security.user.saml.signingCredentials.certificateLocation
Certificate location for signing SAML request.
- efm.security.user.saml.displayNameAttribute

Name of the attribute field of the SAML response which can be used to populate the display name of the user.

Edge Flow Manager supports SAML metadata based configuration. SAML metadata is an XML document which contains information necessary for interacting with SAML-enabled identity providers. To obtain such a metadata file, you need to create a new application integration at your identity provider. For more information, see [IdP documentation](#).

To configure the application at the IdP, the following Edge Flow Manager specific properties are needed:

- Single sign-on URL

This property is also known as SAML Assertion Consumer Service (ACS) URL. In case of localhost, it is <https://localhost:10090/efm/login/saml2/sso/efmSaml>.

- Audience URI (SP Entity ID)

By default, this is <https://localhost:10090/efm/saml2/serviceProviderMetadata/efmSaml>.



Note: The address, port, and contextPath can be different based on configuration. This value can be overridden by the efm.security.user.saml.entityId parameter.

After the successful IdP configuration, you can obtain the metadata.xml file. The location of that metadata file should be set in the efm.security.user.saml.metadataLocation property. The value can either be a local file system path or a location hosted by the identity provider.

If the identity provider supports SAML request signing and it is enabled, you can set up the required key and certificate in the efm.security.user.saml.signingCredentials.* properties. The values should be file system locations, except the privateKeyPassword.

Without additional configuration, the user name is equal to the display name in Edge Flow Manager. If you want to provide a different display name, set up an SAML attribute at the IdP and set the name of the SAML attribute in the efm.security.user.saml.displayNameAttribute property.

Related Information

[SSO identity provider setup](#)

[TLS configuration for EFM](#)

Configuring Knox SSO

Learn about the properties that you need to set for configuring Knox SSO.

About this task

Edge Flow Manager supports Knox SSO for end user authentication with the following limitations:

- Knox cannot be used as a gateway that forwards requests to Edge Flow Manager.
- Knox must be accessible using the same hostname as Edge Flow Manager (a different port is fine). Otherwise, the authentication token issued by Knox, which is stored in a browser cookie, cannot be passed to Edge Flow Manager and its authentication fails with a Credentials not present error. This means the following:
 - For Edge Flow Manager clusters, Knox must be accessible through the same load balancer or reverse proxy used to access Edge Flow Manager nodes.
 - For individual, non-clustered Edge Flow Manager instances, Knox must run on the same host as Edge Flow Manager on a different port.

Before you begin

- You have installed Knox.
- You have installed and secured the Edge Flow Manager server to use TLS. For more information on enabling TLS in Edge Flow Manager, see *TLS configuration for Edge Flow Manager*.

Procedure

1. Obtain the Knox SSO token signing certificate in PEM format.

This is sometimes the same as the public certificate used for TLS by Knox, and can therefore be obtained using OpenSSL against the Knox host:

```
openssl s_client -servername HOSTNAME -connect HOST:PORT | sed -ne '/-BEGIN CERTIFICATE-/,/-END CERTIFICATE-/p' > knox_server_cert_in_pem_file_format.pem
```

Sometimes, however, a different signing keypair is configured specifically for Knox SSO signing and must be obtained from that server configuration. Once you have the Knox SSO token signing certificate, save the certificate on the Edge Flow Manager server and ensure that the file is readable by the user running the Edge Flow Manager process.

2. Update the Edge Flow Manager configuration file with the following properties:

```
efm.security.user.knox.enabled=true
efm.security.user.knox.url=https://knox.mycompany.com:8443/gateway/knoxsso/api/v1/webss
efm.security.user.knox.publicKey=path/to/knox_server_cert_in_pem_file_format.pem
efm.security.user.knox.cookieName=hadoop-jwt
efm.security.user.knox.audiences=
```

3. In Cloudera Manager, that manages Knox, update the Knox topology for the Knox SSO service to add the Edge Flow Manager hostname (or Edge Flow Manager load balancer hostname when clustered) to the authorized redirect URLs.

For example:

```
<service>
  <role>KNOXSSO</role>
  ...
  <param>
    <name>knoxssso.redirect.whitelist.regex</name>
```

```

<value>^https?:\/\/(efm\.hostname\.com|localhost|127\.0\.0\.1|:1):[0
-9].*$</value>
</param>
</service>

```

4. Restart Edge Flow Manager and Knox.

Related Information

[TLS configuration for Edge Flow Manager](#)

Configuring mutual TLS authentication

Edge Flow Manager supports mutual TLS (mTLS) authentication in which the client provides the Edge Flow Manager server with a client certificate as part of the TLS handshake, and the client certificate provides the identity of the client. Learn about the properties that you need to set for configuring mTLS.

Edge Flow Manager requires using mTLS for MiNiFi agent authentication as described in *Agent authentication*, and optionally offers using this form of authentication for end users as well. For example, web browsers support loading client certificates that can be passed to a web server when using a web application.

For service accounts, such as those that programmatically interact with the Edge Flow Manager RESTful API for automation or monitoring purpose, mutual TLS authentication must be used, and can be enabled in addition to another mechanism such as one of the SSO login options.

Before configuring mTLS authentication, Edge Flow Manager should already be configured to use TLS. For more information on enabling TLS in Edge Flow Manager, see *TLS configuration for Edge Flow Manager*.

To enable mTLS authentication in Edge Flow Manager, set the following property in the efm.properties file:

```
efm.security.user.certificate.enabled=true
```

Again, this can be enabled simultaneously with another method of authentication, such as OIDC or SAML SSO, in the case that RESTful API service accounts use mTLS but web users login with SSO using username and password credentials.

Edge Flow Manager trusts client certificates signed by a Certificate Authority (CA) or intermediate authority present in the Edge Flow Manager truststore. For information on generating certificates, see *TLS keys and certificates*. For more information about configuring the Edge Flow Manager truststore, see *TLS configuration for Edge Flow Manager*.

When a client authenticates using mTLS, the client certificate DN is the user identity. For example, CN=monitoring-service, OU=systems, O=cloudera. Therefore, an admin must add a user with an identity equal to the client certificate DN in order to grant this type of user access to parts of Edge Flow Manager. For more information on creating users and assigning policies, see *Access control policies*.

Here is an example of accessing the Edge Flow Manager REST API using curl when mTLS authentication is enabled:

```

curl \
--cacert /path/to/ca-trust-cert.pem \
--cert /path/to/user-cert.pem \
--key /path/to/user-key.pem \
--pass password \
https://localhost:10090/efm/api/access

# JSON response
{"identity": "CN=user, OU=systems, O=cloudera", "anonymous": false, "globalPermissions": {"accessAdministration": false}}

```

Related Information

[Agent authentication](#)

[TLS configuration for Edge Flow Manager](#)

- [TLS keys and certificates](#)
- [Access control policies](#)

Configuring proxy authentication

Learn about the properties that you need to set for configuring proxy authentication.



Important: Proxy Authentication is being deprecated and will be removed in a next Edge Flow Manager release.

Edge Flow Manager can be configured to trust an HTTP reverse proxy to authenticate users externally and pass the user details with each request. This is useful in some SSO environments in which OIDC or SAML is not an option, and some gateway, proxy, or central web service handles user authentication to multiple backend services.

You need to set the following configuration options for using proxy authentication:

```
efm.security.user.proxy.enabled=true
efm.security.user.proxy.headerName=x-webauth-user
efm.security.user.proxy.ipWhitelist=
efm.security.user.proxy.dnWhitelist[0]=
```

Where,

- `efm.security.user.proxy.enabled`

Whether proxy authentication is enabled.

- `efm.security.user.proxy.headerName`

Case-insensitive header name set by the proxy holding the end user identity.

- `efm.security.user.proxy.ipWhitelist`

Limits trusted proxy IP addresses to prevent spoofing the user header. Comma-separated or multiple properties using the `ipWhitelist[n]` syntax:

- `efm.security.user.proxy.ipWhitelist[0]=`
- `efm.security.user.proxy.ipWhitelist[1]=`
- `efm.security.user.proxy.dnWhitelist[0]..[n]`

Limits trusted proxy client certificate DNs to prevent spoofing the user header. Use the `dnWhitelist[n]` syntax as it is common for certificate DNs to contain commas.

If you are using proxy authentication, Cloudera strongly recommends that you use either the DN whitelist or IP whitelist feature to specify trusted reverse proxies. If you are not using a whitelist, it is assumed that you are using some other networking mechanism to ensure that all authenticated requests are coming from a trusted client, such as only binding the Edge Flow Manager server to localhost and running the authenticating proxy on the same machine on a different network interface.

The following is a curl example of passing the proxy user header to the `/api/access` endpoint that returns the recognized current user:

```
curl -H "X-WEBAUTH-USER: alice"
      https://localhost:10090/efm/api/access

# Response:
{"identity": "alice", "anonymous": false}
```

As you can see, this header can be added to any request, which is why DN whitelisting, IP whitelisting, or localhost binding should be used with proxy authentication.

Configuring LDAP authentication

Learn about the properties that you need to set for configuring LDAP authentication.

Before you begin

Edge Flow Manager supports username/password authentication using LDAP. Before configuring LDAP, ensure that Edge Flow Manager is already configured for TLS and user authentication is enabled with the following properties:

- **efm.security.user.auth.enabled**

Set to true to enable Edge Flow Manager user authentication. You need to configure an authentication method such as MTLS, OIDC, SAML, KNOX, or LDAP.

- **efm.security.user.auth.authTokenExpiration**

Edge Flow Manager issues access tokens when a user is authenticated. Specify the duration of the token's validity. The default value is 12 h.

Procedure

1. Update the Edge Flow Manager configuration file with the following LDAP authentication properties.

- **efm.security.ldap.auth.enabled**

Use it to enable LDAP authentication in Edge Flow Manager.

- **efm.security.ldap.auth.searchFilter**

Use this filter to search for users against efm.security.ldap.user.searchBase (for example: uid={0}). The user's specified name is inserted into '{0}'.

2. Configure the following LDAP user search properties.

- **efm.security.ldap.user.searchBase**

Define the base DN to search for users (for example: ou=users,o=efm).

- **efm.security.ldap.user.objectClass**

Specify the object class used to identify users (for example: person).


- **efm.security.ldap.user.searchScope**

Set the search scope for user searches. Possible values are ONE_LEVEL, OBJECT, or SUBTREE.

- **efm.security.ldap.user.identityAttribute**

Optionally, you can specify the attribute used to extract user identity (for example: cn). If not set, the entire DN is used.

3. Once EFM is started with the above configuration, open the site to get redirected to the login page.



On this page, you can log in with your username (as defined by the LDAP identity attribute value) and your password.

Related Information

[TLS configuration for Cloudera Edge Management](#)

[Initial admin identities](#)

[Managing user groups using LDAP](#)

Access control policies

Edge Flow Manager uses role based access control at the agent class level. This means that everything in Edge Flow Manager is tied to agent classes. On top of restricting access to specific endpoints and functionality, all data returned by Edge Flow Manager is also filtered based on the agent classes the given user has access to. All entities, such as flows, events, and parameters are mapped to agent classes by Edge Flow Manager so access can be determined based on that.

Edge Flow Manager recognizes agent class viewer, designer, and operator roles along with the global administrator role. For more information, see *Policies for agent class roles*.

Related Information

[Policies for agent class roles](#)

Access control bootstrapping

After Edge Flow Manager is secured, you have to set up and configure the access control policies and permissions in a system.

Access control bootstrapping involves two key aspects: authentication and authorization.

- Authentication ensures that Edge Flow Manager can verify the identity of the client or the user using configured credentials, as detailed in the *User authentication* documentation.
- Authorization determines whether the authenticated user is allowed to perform specific actions on the requested data. Authorization in Edge Flow Manager is driven by local access control policies. To grant these policies to users, you need to establish an initial admin account with the authority to set up user access. This section provides an overview of that process.

Related Information

[User authentication](#)

Initial admin identities

To be able to register new users and assign roles to them, first you need to set up an initial admin identity. This initial admin has comprehensive access rights and can assign roles and administrative privileges to others as needed. After the initial setup, you can remove this configuration if needed.

You can configure initial admin identities in the efm.properties file.

- `efm.security.user.auth.adminIdentities`

A comma separated list of identities needed for initial admins that can configure other user and group access policies in Edge Flow Manager. For example, `efm.security.user.auth.adminIdentities=admin@cloudera.com`. If admin identities contain special characters such as a comma (,), you can use the following alternative property key format:

- `efm.security.user.auth.adminIdentities[0]=CN=admin1, OU=systems, O=cloudera`
- `efm.security.user.auth.adminIdentities[1]=CN=admin2, OU=systems, O=cloudera`
- `...`
- `efm.security.user.auth.adminIdentities[n]=CN=adminN, OU=systems, O=cloudera`

Starting EFM with this property and logging in with the predefined identity grants you administrator access.

- `efm.security.user.auth.autoRegisterNewUsers`

It controls whether you create each user manually in the Administration page, or the system should do this automatically after the first login attempt for each user. This is a convenience functionality supported by the OIDC and SAML methods.

The following image shows the Administration page after initial admin login:

You can also configure initial admin permissions at group level. To do this, you need to set the following properties:

```
efm.security.user.auth.groups.manager=EXTERNAL
efm.security.user.auth.groups.adminIdentities=Admin-Group-Name
```

Where,

- `efm.security.user.auth.groups.manager`

It indicates that user group management is handled externally by the IdP or LDAP. Its value can be INTERNAL, EXTERNAL, or LDAP. The default value is INTERNAL.

- `efm.security.user.auth.groups.adminIdentities`

A comma separated list of group names needed for initial admins that can configure other user and group access policies in Edge Flow Manager. If group names contain special characters such as a comma (,), you can use the following alternative property key format:


- `efm.security.user.auth.groups.adminIdentities[0]=Group,1`
- `efm.security.user.auth.groups.adminIdentities[1]=Group,2`
- `efm.security.user.auth.groups.adminIdentities[N]=Group,N`

First login with a new user


When a new user logs in for the first time, even though they are recognized by the identity provider, Edge Flow Manager treats them as an unknown user. While the login itself may be successful, an authorization error occurs because the user does not yet have access to any Edge Flow Manager resources or functionalities.

An administrator needs to create an Edge Flow Manager user with a matching identity and grant that user access to an agent class(s).

The following image shows the Administration page after initial admin login:



With the `efm.security.user.auth.autoRegisterNewUsers` property set to true, after the first login, the Edge Flow Manager user is automatically available in the admin view and policies can be assigned to it, as shown in the following image:



The user rights are assigned to the users based on the configured state when the login happens. This means that if policies are changed by an administrator, a re-login is required to issue a new token based on the new policies. After this, the user has access to filtered data based on the assigned policies. Everything is assigned based on agent class, so if users have no assigned role for a given agent class, they do not see anything related to it.

User management

Authorization in Edge Flow Manager is linked to roles assigned to agent classes. These roles must be associated with authenticated users. While the identity provider can recognize these users to support the authentication process, Edge Flow Manager remains responsible for directly managing the permissions of each valid user.

The following sections explain how to manage users.

Creating users

Learn how to create a new user and define a unique identity and display name for that user.


Procedure

1. Click Administration from the left navigation in the Edge Flow Manager UI.

The Administration page appears.

2. Click New User in the Users/Groups tab to create a new user.

The New User dialog appears.



3. Enter the unique identity of the user.

The identity should be the unique identifier for the user provided by the identity provider, typically an email address. When using mutual TLS authentication, the identity should be the DN of the client certificate.

4. Enter the display name of the user.

The display name can be set to anything and represents the user in other places where the user name appears in the application. If you create a new user before the initial login, you can prevent the authorization error described above.

5. Click Create to create the new user.

Editing users

Learn how you can assign policies and roles to a user you created.

Procedure

1. Click Administration from the left navigation in the Edge Flow Manager UI.

The Administration page appears.

2. In the Users/Groups tab, click the [edit] icon next to a user to edit the user.

The user page appears as shown in the following image:

3. Edit the name of the user.
4. Click the Grant this user Administrator privilege checkbox to grant administrator privileges to the given user.
5. Click New Policy to assign policies to the given user (specific role to the given agent class).
6. Click Add to Group to add a given user to a group (all of the roles from the group are inherited by the user).



Note:

Adding and removing members from groups are disabled when the `efm.security.user.auth.groups.manager` Edge Flow Manager property is set to *EXTERNAL* or *LDAP*.

7. Click Apply.

User group management

Managing access through groups is very similar to direct user access management. This is preferred when you need to manage access for multiple users. Users inherit changes made to the group, so no direct changes are needed on the individual user level.

The following sections explain how to manage user groups.

Creating user groups

Learn how to create a new user group.

Procedure

1. Click Administration from the left navigation using the Edge Flow Manager UI.

The Administration page appears.

- Click New User Group, in the Users/Groups tab to create a new group.

The screenshot shows the Cloudera Edge Management interface. On the left, there is a dark sidebar with icons for Monitor, Design, and Administration. The main area is titled 'Administration' and has two tabs: 'USERS/GROUPS' (which is selected) and 'AGENT CLASSES'. The 'USERS/GROUPS' tab contains two sections: 'Users' and 'User Groups'. The 'Users' section lists 'Admin User' and 'test@cloudera.com' with their identities and administrator status. The 'User Groups' section lists 'Admin Group' and 'test group' with their member counts and administrator status. A modal dialog box is open in the center, titled 'New User Group', with a text input field containing 'Enter a unique name' and a note 'Keep this dialog open after creating the group.' with a checkbox. At the bottom of the dialog are 'Cancel' and 'Create' buttons.

- Enter a name for the user group.

Note: The name must be unique because it represents the group in other places where the group name appears in the application.

- Click Create.

Note:

Group creation is disabled when the `efm.security.user.auth.groups.manager` Edge Flow Manager property is set to *EXTERNAL* or *LDAP*.


Editing user groups

Learn how to assign policies and roles to user groups and add users to these groups.

Procedure

- Click Administration from the left navigation in the Edge Flow Manager UI.
The Administration page appears.
- In the Users/Groups tab, click the [edit] icon next to a user group to edit the user group.
- Edit the name of the user group.


4. Click the Grant all group members Administrator privilege checkbox to grant administrator privileges to all group members.



The screenshot shows the 'Administration' section of the Cloudera Edge Management interface. On the left, there are navigation links for Monitor, Design, and Administration. The main area is titled 'Administration' and has tabs for 'USERS/GROUPS' and 'AGENT CLASSES'. Under 'USERS/GROUPS', there is a 'Users' section with a table showing two users: 'Admin User' and 'Test User'. A 'New User' button is available. On the right, there is a detailed view for the 'Admin group'. It shows the group name 'Admin group' and a note: 'All Group Members will have Administrator privileges'. A checkbox labeled 'Grant all group members Administrator privilege' is checked and highlighted with a blue oval. Below this, there is a 'Policies' section and a 'Group Members (2)' section listing 'admin@cloudera.com' and 'test@cloudera.com'.

5. Click New Policy to assign policies to the group (specific role to the given agent class).


6. Click Add Members to add users to the group (all of the roles from the group are inherited by the members)



Note:

Adding and removing members from groups are disabled when the `efm.security.user.auth.groups.manager` Edge Flow Manager property is set to *EXTERNAL* or *LDAP*.

Alternatively, you can edit a user to add the user to a group.



7. Click Apply.

Managing user groups using IdP

Learn how to enable user group management through your Identity Provider (IdP).

About this task

In the case of OIDC / SAML providers, user groups and assignments can be exclusively managed externally using the IdP. This means that user groups can only be added or modified by the IdP, and the assignment of users to groups can solely be performed through the IdP. However, you still retain the capability to assign policies to users and groups within Edge Flow Manager.

Before you begin

Ensure that you have configured the following parameters appropriately:

For OIDC:

- efm.security.user.oauth2.scopes
- efm.security.user.oauth2.groupAttribute

For more information, see *Configuration of OpenID Connect SSO*.

For SAML:

- efm.security.user.saml.groupAttribute

For more information, see *Configuration of SAML 2.0 SSO*.

To enable Group Management by IdP, set the following properties in the efm.properties file:

```
efm.security.user.auth.groups.manager=EXTERNAL
efm.security.user.auth.groups.filter=.*
```

Where,

- efm.security.user.auth.groups.manager

It indicates how user group management is handled: either internally or externally. When the value is set to EXTERNAL, user group management is handled by IdP. When the value is set to INTERNAL, Edge Flow Manager disregards any group information received from the IdP. The default value is INTERNAL.

- efm.security.user.auth.groups.filter

Users might be assigned to multiple groups on the IdP side, but Edge Flow Manager may only need to consider a few of these groups. You can use a regular expression to define which groups should be registered in EFM. The regex allows you to specify a pattern, and only the groups that match the defined pattern will be registered in Edge Flow Manager.



Note:

User groups and individual user-to-group assignments are updated when the user logs in to Edge Flow Manager. As a result, any changes to group-related data in the IdP will only become visible in Edge Flow Manager after the user logs in.

Related Information

[Configuration of OpenID Connect SSO](#)

[Configuration of SAML 2.0 SSO](#)

[Initial admin identities](#)

Managing user groups using LDAP

Learn how to enable user group management using the Lightweight Directory Access Protocol (LDAP).

About this task

Edge Flow Manager can be configured to retrieve group assignments from LDAP. This implies that user groups can only be added or modified using LDAP, and user-group assignments can exclusively be managed through LDAP. However, you still retain the ability to assign policies to users and groups within Edge Flow Manager.

Procedure

1. Enable user group management by LDAP.

To enable user group management using LDAP, set the following property in the efm.properties file:

```
efm.security.user.auth.groups.manager=LDAP
```

2. Configure LDAP integration.

For a successful integration, make sure that the following properties are accurately configured.

Basic properties:

efm.security.ldap.url

Enter a comma-separated list of LDAP server URLs (for example: ldap://<hostname>:<port>)

efm.security.ldap.syncInterval

Specify the duration of time between synchronizing users and groups (for example: 30 m). The minimum allowable value is 30 seconds and the default value is 30 minutes.

efm.security.ldap.managerDn

Provide the Distinguished Name (DN) of the manager used to bind to the LDAP server to search for users and groups.

efm.security.ldap.managerPassword

Enter the password of the manager used to bind to the LDAP server to search for users and groups.

efm.security.ldap.authenticationStrategy

Select an authentication strategy for connecting to the LDAP server.

Possible values:

- ANONYMOUS
- SIMPLE
- LDAPS
- START_TLS

efm.security.ldap.referralStrategy

Select a strategy for handling LDAP referrals.

Possible values:

- FOLLOW (default value, automatically follow any referrals)
- IGNORE (ignore referrals)
- THROW (throw an error if a referral occurs)

efm.security.ldap.connectTimeout

Set the duration of the connection timeout. The default value is 10 seconds.

efm.security.ldap.readTimeout

Set the duration of the read timeout. The default value is 10 seconds.

efm.security.ldap.pageSize

Optionally, you can set the page size when retrieving users and groups. If not specified, no paging is performed.

efm.security.ldap.groupMembershipCaseSensitive

Indicate whether group membership decisions should be case-sensitive. The default value is false.

TLS properties

These properties are required when efm.security.ldap.authenticationStrategy is set to LDAPS or START_TLS.

efm.security.ldap.tls.keyStore

Specify the path to the keystore used when connecting to LDAP.

efm.security.ldap.tls.keyStorePassword

Set the password for the keystore used when connecting to LDAP.

efm.security.ldap.tls.keyStoreType

Define the type of the keystore used when connecting to LDAP. Possible values are BCFKS, PKCS12, or JKS.

efm.security.ldap.tls.trustStore

Provide the path to the truststore used when connecting to LDAP.

efm.security.ldap.tls.trustStorePassword

Set the password for the truststore used when connecting to LDAP.

efm.security.ldap.tls.trustStoreType

Specify the type of the truststore used when connecting to LDAP. Possible values are BCFKS, PKCS12, or JKS.

efm.security.ldap.tls.tlsProtocol

Select the protocol to use when establishing LDAP connections. Possible values are TLS, TLSv1_1, or TLSv1_2.

efm.security.ldap.tls.shutdownGracefully

Determine whether TLS should be shut down gracefully before the target context is closed. The default setting is false and applies exclusively to the START_TLS authentication strategy.

Search properties

Synchronizing users and groups is possible through user, group, or both user and group searches, depending on your LDAP scheme and configuration. However, it is essential to configure at least one of these properties to enable user and group synchronization.

User search

efm.security.ldap.user.searchBase

Specify the base DN for searching users (for example: ou=users, o=efm).

efm.security.ldap.user.objectClass

Define the object class for identifying users (for example: person).

efm.security.ldap.user.searchScope

Set the search scope for searching users. Possible values are ONE_LEVEL, OBJECT, or SUBTREE.

efm.security.ldap.user.searchFilter

Apply a filter for searching users in the User Search Base (for example: (memberof=cn=team1,ou=groups,o=efm)).

efm.security.ldap.user.identityAttribute

Optionally, you can specify the attribute used to extract user identity (for example: cn). If not set, the entire DN is used.

efm.security.ldap.user.groupNameAttribute

Optionally, you can define the attribute used to establish group membership (for example: memberof). If not set, group memberships are calculated based on efm.security.ldap.group.memberAttribute. If set, the value of this property is the name of the attribute in the user LDAP entry that associates them with a group. The value of this user attribute could be a DN or group name for instance. The expected value is configured in efm.security.ldap.user.referencedGroupAttribute.

efm.security.ldap.user.referencedGroupAttribute

If not set, the value of the attribute defined in efm.security.ldap.user.groupNameAttribute is expected to be the full DN of the group. If set, this property defines the attribute of the group LDAP entry to which the value of the attribute defined in

efm.security.ldap.user.groupNameAttribute refers (for example: name). The use of this property requires that efm.security.ldap.group.searchBase is also configured.

Group search

efm.security.ldap.group.searchBase

Specify the base DN for group searches (for example: ou=users,o=efm).

efm.security.ldap.group.objectClass

Identify the object class for groups (for example: groupOfNames).

efm.security.ldap.group.searchScope

Define the search scope for group searches. Possible values are ONE_LEVEL, OBJECT, or SUBTREE.

efm.security.ldap.group.searchFilter

Optionally, you can filter for group searches against efm.security.ldap.group.searchBase.

efm.security.ldap.group.nameAttribute

Optionally, you can extract group names using the specified attribute (for example: cn). If not set, the entire DN is used.

efm.security.ldap.group.memberAttribute

Optionally, you can specify an attribute for defining group membership (for example: member). If not set, group membership will not be calculated through the groups. Instead, it relies on group membership defined using efm.security.ldap.user.groupNameAttribute. If set, the value of this property is the name of the attribute in the group LDAP entry that associates users with groups. The value of this group attribute can be a DN or memberUid, depending on your configuration (for example: member: cn=User 1,ou=users,o=efm vs. memberUid: user1).

efm.security.ldap.group.referencedUserAttribute

If not set, the value of the attribute defined in efm.security.ldap.group.memberAttribute is expected to be the full DN of the user. If set, this property defines the attribute of the user LDAP entry referenced by efm.security.ldap.group.memberAttribute (for example: uid). Using this property requires that efm.security.ldap.user.searchBase is also configured (for example: member: cn=User 1,ou=users,o=efm vs. memberUid: user1).

Agent class roles policies

Learn about the different policies of an agent class that you can assign to users, and understand the specific functions of each policy.

Policies are linked to agent classes, and Edge Flow Manager currently supports three roles:

- A Viewer can view designs and monitor events for the assigned agent class, but can not edit or publish the flows. Essentially, viewers cannot make any modifications in the system.
- A Designer can view and edit designs, monitor events for the assigned agent class, but cannot publish flows.
- An Operator can monitor events, publish designs for the assigned agent class (without editing), and can modify flow and parameter mappings.


Depending on the use case, it is possible to have multiple roles for the same user. For example, if you do not want to differentiate between a designer and an operator for a given agent class (you want the same person to edit and publish the flow), you can do that by assigning both roles to the user. The following image shows that one user can have multiple roles on the same agent class:

The screenshot shows the 'Administration' section of the Cloudera Edge Management interface. On the left, a sidebar lists 'Monitor', 'Edge Events', 'Design', 'Agent Manager', 'Resource Manager', and 'Administration'. The 'Administration' item is selected. The main area is titled 'Administration' and shows 'USERS/GROUPS' and 'AGENT CLASSES' tabs. Under 'USERS/GROUPS', the 'Users' section lists 'Test User', 'Admin EFM', 'User One', 'User Two', and 'User Three' with their respective identities and roles. A 'Policies' section shows 'Class A' assigned to 'Designer', 'Operator', and 'Viewer' roles. A 'Group Membership' section lists 'CEM', 'CEM-DemoUsers', and 'CEM-JAVA'. An 'Apply' button is at the bottom right.


The flow designs and event lists are filtered based on authorization. So, only those items are visible, which are related to the agent class the user is assigned to. In the following case, only Class A is visible as roles are assigned only to Class A for this user (though Class B and Class C exist as well for this user).

The screenshot shows the 'Dashboard' section of the Cloudera Edge Management interface. On the left, a sidebar lists 'Monitor', 'Edge Events', 'Design', 'Agent Manager', and 'Resource Manager'. The 'Agent Manager' item is selected. The main area is titled 'Dashboard' and shows the 'Agent Manager' section. It includes a search bar 'Search by class name', a table with columns 'Status', 'Class Name', 'Number of Agents', 'Last Flow Updated', and 'Updated Agents'. The table shows two rows: 'Good Health' for 'Class A' (1 agent, last updated 12 seconds ago) and 'Unknown Health' for 'Unassigned' (0 agents, last updated 12 seconds ago). A pagination bar at the bottom indicates 10 items per page, 1-2 of 2, and navigation arrows.


The following image shows that the users with viewer or designer roles can not publish a flow, as the Publish option is disabled:



The following image shows that users with viewer or operator roles can not edit the flow, as all configurations are disabled;



The following image shows that users with operator role can view and publish the flow but not edit:




Assigning policies to a user

Learn how to select an agent class for a user and assign roles or policies to that user.

Procedure

1. Click Administration from the left navigation in the Edge Flow Manager UI.
The Administration page appears.
2. In the Users/Groups tab, click New User.
Alternatively, you can click the edit icon for an existing user.
The user page appears.
3. Click New Policy.
The New Policy page appears.



4. Select a class for the user.

5. Select a role for the user.

You can assign multiple roles to a user for the same class.

6. Click Apply to save the changes.



Note: Logging in with a prepared user (matching happens based on identity) gives the user the predefined roles, so there is no initial authorization error.

Assigning policies to a user group

Learn how to select an agent class for a user group and assign roles or policies to that user group.

Procedure

1. Click Administration from the left navigation in the Edge Flow Manager UI.
The Administration page appears.

2. In the Users/Groups tab, click New User Group.

Alternatively, you can click the edit icon for an existing user group.

The user group page appears.

3. Click New Policy.

The New Policy page appears.

4. Select a class for the user group.

The screenshot shows the 'Administration' section of the Cloudera Edge Management interface. In the 'USERS/GROUPS' tab, a 'test group' is selected. A 'New Policy' dialog is open, showing the 'test group' with 0 group members. The 'Class' dropdown is open, displaying a list of available classes: Class A, Class B, Class C, dev-mode-agent-class, and Unassigned. The 'Role' section is visible on the right side of the dialog.

5. Select a role for the user group.

You can assign multiple roles to a group for the same class.

The screenshot shows the 'Administration' section of the Cloudera Edge Management interface. In the 'USERS/GROUPS' tab, a 'test group' is selected. A 'New Policy' dialog is open, showing the 'test group' with 0 group members. The 'Class' dropdown is set to 'Class A'. The 'Role' section is open, showing 'Viewer' selected. The 'Create' button is highlighted at the bottom of the dialog.

6. Click Apply to save the changes.

The screenshot shows the 'Administration' page with the 'USERS/GROUPS' tab selected. On the left, a sidebar shows 'Admin User' and '1.3.0-0-SNAPSHOT'. The main area displays a table of users with columns 'Name', 'Identity', and 'Role'. A 'New User' button is at the top right. On the right, a detailed view for 'test group' shows its name, a checkbox for 'Grant all group members Administrator privilege', and a 'Policies' section. The 'Policies' section lists 'Agent Class' and 'Role' for 'Class A' (Viewer). Below is a 'Group Members (0)' section with an 'Add Member' button. A blue callout box points to the 'Apply' button at the bottom right with the text 'Click on the Apply button to save changes'.

In the user edit view in the policies section, you can see which policies are direct and which are inherited through group assignment.

The screenshot shows the 'Administration' page with the 'USERS/GROUPS' tab selected. The main area displays a table of users. On the right, a detailed view for 'Test User' shows its name, a checkbox for 'Grant this user Administrator privilege', and a 'Policies' section. The 'Policies' section lists 'Agent Class', 'Role', and 'Group Assignment' for 'Class A' (Viewer), 'Class B' (Designer, 'test group 2'), and 'Class C' (Viewer, 'test group'). Below is a 'Group Membership (2)' section with an 'Add to Group' button. A blue callout box points to the 'Apply' button at the bottom right with the text 'Click on the Apply button to save changes'.

Assigning policies to agent classes

Learn how you can manage access control on the agent class level.


Procedure

1. Click Administration in the Edge Flow Manager UI.

The Administration page appears.

2. Go to Agent Classes tab.

The list of agent classes with number of deployed agents appears.




Class Name	Agents
Unassigned	0
Class A	1
Class B	1
Class C	1

You can manage user or group level assignments for a specific agent class.

3. Click the edit icon beside the class you want to modify.

The class dialog appears.




User/Group	Role
Test User	Operator

4. Click New Policy.


The New Policy page appears.

5. Select a user or user group for the agent class.



The screenshot shows the Cloudera Edge Management interface. On the left, there's a sidebar with 'Monitor', 'Design', and 'Administration' buttons. The main area has tabs for 'USERS/GROUPS' and 'AGENT CLASSES', with 'AGENT CLASSES' selected. Under 'Agent Classes', there are four entries: 'Unassigned' (0 agents), 'Class A' (1 agent), 'Class B' (0 agents), and 'Class C' (0 agents). A 'New Policy' dialog is open for 'Class A'. It shows 'Class A' with 1 agent. The 'User/Group' field is active, containing a dropdown menu with 'Admin group' selected. Other options in the dropdown include 'Admin User', 'test group', 'test group 2', and 'Test User'. The 'Policies' table on the right shows a single entry for 'Test User' with the 'Role' set to 'Operator'.

6. Select a role for the user or user group.



The screenshot shows the same interface as the previous one, but the 'New Policy' dialog now shows 'Admin Group' selected in the 'User/Group' dropdown. Under the 'Role' section, the 'Designer' radio button is selected, while 'Viewer' and 'Operator' are unselected. The 'Create' button is visible at the bottom of the dialog. The background shows the 'Agent Classes' list and the 'Policies' table.

You can assign multiple roles to a user or group for the same class.

- Click Apply to save changes.

The screenshot shows the 'Agent Classes' section of the Cloudera Edge Management interface. On the left, there's a sidebar with 'Monitor', 'Design', and 'Administration' buttons, and a status message '1.3.0-SNAPSHOT'. The main area has tabs for 'USERS/GROUPS' and 'AGENT CLASSES', with 'AGENT CLASSES' selected. A table lists 'Agent Classes' with columns for 'Class Name' and 'Agents'. The classes listed are 'Unassigned' (0 agents), 'Class A' (1 agent), 'Class B' (1 agent), 'Class C' (1 agent), and 'dev-mode-agent-class'. To the right, a detailed view of 'Class A' shows 'Policies' for 'User/Group' 'Admin Group' (Role 'Designer') and 'Test User' (Role 'Operator'). A 'New Policy' button is also present. A callout box with the text 'Click on the Apply button to save changes' points to the 'Apply' button at the bottom right of the interface.

SSO identity provider setup

To integrate Edge Flow Manager with a third-party single sign-on (SSO) identity provider, you need to add Edge Flow Manager as an application client to the identity provider. This configuration allows Edge Flow Manager to facilitate SSO logins by redirecting users to the identity provider and retrieving user details from the provider's user directory for use within Edge Flow Manager.

The supported protocols for identity provider integration are OpenID Connect (OIDC) and SAML 2.0. OIDC is sometimes referred to as OAuth2 login because it extends the authorization protocols in OAuth2. OIDC and SAML 2.0 are industry standard protocols supported by the majority of modern enterprise identity providers including Okta, Google, GitHub, Azure Active Directory and others.

For the latest guidance on configuring Edge Flow Manager as an application client for your SSO identity provider, see the *Identity Provider documentation*.

Okta integration using OIDC

To integrate Edge Flow Manager with Okta, Cloudera recommends using the Okta Application Integration Wizard. This wizard simplifies the process of adding Edge Flow Manager as a custom application using the OIDC protocol for integration.

For the latest guidance on how to add Edge Flow Manager as a custom application using OIDC, see [Create OIDC app integrations using AIW](#).

You need to enter few pieces of information about Edge Flow Manager, asked by Okta. The following table specifies the values to provide:

Property	Value
App Integration Name	Cloudera Edge Flow Manager (or whichever name you prefer)
Grant Type	Authorization Code
Sign-in redirect URIs	https://efm-host:efm-port/efm/login/oauth2/code/efm-oidc , https://efm-host:efm-port/efm/*

Property	Value
Sign-out redirect URIs	<code>https://{{efm-host:efm-port}}/efm/ui#/logged-out</code> , <code>https://{{efm-host:efm-port}}/efm/*</code>
Client Credentials > Client ID	Set in Okta to any value, for example, efm, and then copy into the efm.properties file as <code>efm.security.user.oidc.clientId</code>
Client Credentials > Client Secret	Generate in Okta and copy the value into the efm.properties file as <code>efm.security.user.oidc.clientSecret</code>

After completion, configure Edge Flow Manager by following the instructions in *Configuration of OpenID Connect SSO*.

Related Information

[Configuration of OpenID Connect SSO](#)

Okta Edge Flow Manager integration using SAML

To integrate Edge Flow Manager with Okta, Cloudera recommends using the Okta Application Integration Wizard. This wizard simplifies the process of adding Edge Flow Manager as a custom application using SAML 2.0.

For the latest guidance on how to add Edge Flow Manager as a custom application using SAML, see [Create SAML app integrations using AIW](#).

You need to enter few pieces of information about Edge Flow Manager, asked by Okta. The following table specifies the values to provide:

Property	Value
App Integration Name	Cloudera Edge Flow Manager (or whichever name you prefer)
Single sign on URL	<code>https://localhost:10090/efm/login/saml2/sso/efm-saml</code>
Audience URI (SP Entity ID)	<code>https://localhost:10090/efm/saml2/service-provider-metadata/efm-saml</code>
Attribute Statements (optional)	<p>Edge Flow Manager contains an optional property in the efm.properties file called <code>efm.security.user.saml.displayNameAttribute</code>. This controls what name gets set in Edge Flow Manager the first time a user logs in using SAML SSO. In order to use this, set an attribute in SAML settings in Okta to hold the user's display name and then update Edge Flow Manager to set the <code>displayNameAttribute</code> to the same attribute key/name. For example:</p> <p>In Okta:</p> <p>Name: <code>first_name</code></p> <p>Value: <code>user.firstName</code></p> <p>In the efm.properties file:</p> <p><code>efm.security.user.saml.displayNameAttribute=first_name</code></p>

After completion, configure Edge Flow Manager by following the instructions in *Configuration of SAML 2.0 SSO*.

Related Information

[Configuration of SAML 2.0 SSO](#)