

Cloudera Runtime 7.2.9

Starting Apache Hive

Date published: 2019-08-21

Date modified: 2021-04-28

CLOUDERA

<https://docs.cloudera.com/>

Legal Notice

© Cloudera Inc. 2024. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

Start Hive using a password.....	4
Accessing Hive from an external node.....	7
Run a Hive command.....	8

Start Hive using a password

You start the Hive shell using a Beeline command to query Hive as an end user authorized by Apache Ranger. As administrator, you set up the end user in the operating system and in Ranger.

About this task

Before starting Hive for the first time, you might want to check that you are covered by Ranger policies required for basic operations as shown in the following steps. All users need to use the default database, perform operations such as listing database names, and query the information schema. The preloaded default database tables columns and information_schema database Ranger policies cover group public (all users). If these policies are disabled, you cannot use the default database, perform basic operations such as listing database names, or query the information schema. For example, if the default database tables columns policy is disabled, the following error appears if you try to use the default database:


```
hive> USE default;
Error: Error while compiling statement: FAILED: HiveAccessControlException
Permission denied: user [hive] does not have [USE] privilege on [default]
```

Procedure

1. Access the Ranger Console: click the Ranger Admin web UI link, enter your user name and password, then click Sign In.
2. On the far right, click Ranger cm_hive and in Allow Conditions, edit all - database, table, column.

Policy ID	Policy Name	Policy Labels	Status	Audit Logging	Roles	Groups	Users	Action
7	all - hiveservice	--	Enabled	Enabled	--	--	hive rangerlookup impala	  
8	all - global	--	Enabled	Enabled	--	--	hive rangerlookup impala	  
9	all - database, table, column	--	Enabled	Enabled	--	admins	hive rangerlookup impala	  

3. Add your user or group name to Hive policies to grant full access to Hive.
For example, add the admins group name to the list of groups that can access Hive.




The screenshot shows the 'Edit Policy' interface in the Ranger console. The breadcrumb navigation is 'Service Manager > cm_hive Policies > Edit Policy'. There are two 'Select Roles' input fields. The 'Groups' field is expanded, displaying a list of groups: public, csso_yuhsin, admins (selected), cdpe2euser87444, csso_glekeny, qaas, and csso_preethi. The 'Users' field contains 'hive' and 'rangerlookup'.

- Check that the preloaded default database tables columns and information_schema database policies are enabled for group public.

Policy ID	Policy Name	Policy Labels	Status	Audit Logging	Roles	Groups	Users
7	all - global	--	Enabled	Enabled	--	--	hive beacon dpprofiler hue + More..
8	all - database, table, column	--	Enabled	Enabled	--	--	hive beacon dpprofiler hue + More..
9	all - database, table	--	Enabled	Enabled	--	--	hive beacon dpprofiler hue + More..
10	all - database	--	Enabled	Enabled	--	public	hive beacon dpprofiler hue + More..
11	all - hiveservice	--	Enabled	Enabled	--	--	hive beacon dpprofiler hue + More..
12	all - database, udf	--	Enabled	Enabled	--	--	hive beacon dpprofiler hue + More..
13	all - url	--	Enabled	Enabled	--	--	hive beacon dpprofiler hue + More..
14	default database tables columns	--	Enabled	Enabled	--	public	--
15	Information_schema database ...	--	Enabled	Enabled	--	public	--

- In Environments *your environment your cluster*, click the CM-URL.
- In Cloudera Manager, click Hosts All Hosts.



- Make a note of the IP address or host name of a node in your cluster, for example myhost-vpc.cloudera.com.

8. Use ssh to log into the cluster.

For example:

```
ssh myhost-vpc.cloudera.com
```

You can get help about starting the Hive shell. On the command line, type

```
hive -h
```

Output is:

```
Connect using simple authentication to HiveServer2 on localhost:10000
beeline -u jdbc:hive2://localhost:10000 username password

Connect using simple authentication to HiveServer2 on hs.local:10000 us
ing -n for username and -p for password
beeline -n username -p password -u jdbc:hive2://hs2.local:10012

Connect using Kerberos authentication with hive/localhost@mydomain.com as
HiveServer2 principal
beeline -u "jdbc:hive2://hs2.local:10013/default;principal=hive/localho
st@mydomain.com"

Connect using SSL connection to HiveServer2 on localhost at 10000
beeline "jdbc:hive2://localhost:10000/default;ssl=true;sslTrustStore=/usr/
local/truststore;trustStorePassword=mytruststorepassword"

Connect using LDAP authentication
beeline -u jdbc:hive2://hs2.local:10013/default <ldap-username> <ldap-pas
sword>
```

9. Using the fully qualified domain name or IP address a node in your cluster from Cloudera Manager Hosts Role(s) and looking through the list of roles to find HS2 (Hive on Tez HiveServer2). For example:

Hosts	Count	Roles
ip-10-97-84-212.cloudera.site; ip-10-97-85-[91, 163].cloudera.site	3	 G  DN  G  G  G  G  G  G  G  NM
ip-10-97-85-16.cloudera.site	1	 G  HS2  LB  HS  KTR  KG  HMS  SNN  G  LS  AP  ES  HM  RM  SM  TP  OS  G  HS  G  JHS  RM  ZS  S

This node has the HiveServer role, so you can use the name or IP address in Beeline.

10. Start the Hive shell.

- Use your user name if your cluster security is set up.
- Use the user name hive and no password.

Substitute the name or IP address of your HiveServer host for 10.65.13.98.

Simple authentication:

```
beeline -u jdbc:hive2://10.65.13.98:10000 -n <your user name> -p
```

Kerberos:

```
beeline -u "jdbc:hive2://10.65.13.98:10000/default;principal=hive/_HOST@CLLOUDERA.SITE"
```

11. Enter Hive queries.

```
SHOW DATABASES;
```

```
CREATE TABLE students (name VARCHAR(64), age INT, gpa DECIMAL(3,2));
```

```
INSERT INTO TABLE students VALUES ('fred flintstone', 35, 1.28), ('barney rubble', 32, 2.32);
```

Related Information

[Configure a Resource-based Policy: Hive](#)

Accessing Hive from an external node

In CDP public cloud, most of the services are accessible through the Apache Knox gateway including Apache Hive. You need to know the URL of the Data Hubs cluster to use from an external cluster and the Beeline command to run from an external node.

Before you begin

- In CDP Public Cloud, you must be running the Knox, Hive Metastore, and Hive services.
- The external node must be on a cluster that CDP Public Cloud can access.
- On an external cluster, you must be authorized to access the CDP Public Cloud Data Hub cluster.

...